



# **X264dn, X363dn, X364dn/dw, X463de, X464de, X466de/dte/dwe**

---

## **Technical Reference**

**December 2009**

**[www.lexmark.com](http://www.lexmark.com)**

---

Lexmark and Lexmark with diamond design are trademarks of Lexmark International, Inc., registered in the United States and/or other countries. All other trademarks are the property of their respective owners.

© 2009 Lexmark International, Inc.

All rights reserved.

740 West New Circle Road  
Lexington, Kentucky 40550

## **Edition notice**

December 2009

**The following paragraph does not apply to any country where such provisions are inconsistent with local law:** LEXMARK INTERNATIONAL, INC., PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. Some states do not allow disclaimer of express or implied warranties in certain transactions; therefore, this statement may not apply to you.

This publication could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in later editions. Improvements or changes in the products or the programs described may be made at any time.

References in this publication to products, programs, or services do not imply that the manufacturer intends to make these available in all countries in which it operates. Any reference to a product, program, or service is not intended to state or imply that only that product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any existing intellectual property right may be used instead. Evaluation and verification of operation in conjunction with other products, programs, or services, except those expressly designated by the manufacturer, are the user's responsibility.

For Lexmark technical support, visit **support.lexmark.com**.

For information on supplies and downloads, visit **www.lexmark.com**.

If you don't have access to the Internet, you can contact Lexmark by mail:

Lexmark International, Inc.  
Bldg 004-2/CSC  
740 New Circle Road NW  
Lexington, KY 40550  
USA

© 2009 Lexmark International, Inc.

**All rights reserved.**

## **Trademarks**

Lexmark and Lexmark with diamond design are trademarks of Lexmark International, Inc., registered in the United States and/or other countries.

PCL® is a registered trademark of the Hewlett-Packard Company.

All other trademarks are the property of their respective owners.

## **UNITED STATES GOVERNMENT RIGHTS**

This software and any accompanying documentation provided under this agreement are commercial computer software and documentation developed exclusively at private expense.

# Contents

|   |           |
|---|-----------|
| <b>Edition notice</b> .....                                 | <b>2</b>  |
| <b>Introduction</b> .....                                   | <b>5</b>  |
| Understanding letters after model numbers.....              | 5         |
| <b>Learning about the printer</b> .....                     | <b>6</b>  |
| Finding information about the printer.....                  | 6         |
| <b>Printer Control Language (PCL) page formatting</b> ..... | <b>7</b>  |
| Printable areas.....  | 7         |
| Supported paper and envelope dimensions.....                | 8         |
| <b>Printer Job Language (PJM)</b> .....                     | <b>10</b> |
| PJM commands information.....                               | 10        |
| <b>PostScript (PS) emulation</b> .....                      | <b>11</b> |
| Paper sizes supported.....                                  | 11        |
| PostScript paper tray support.....                          | 12        |
| PostScript envelope size support.....                       | 14        |
| PostScript envelope tray support.....                       | 15        |
| <b>Printer specifications</b> .....                         | <b>17</b> |
| Airflow requirement.....                                    | 17        |
| Noise emission levels.....                                  | 17        |
| Electrical specifications.....                              | 18        |
| Power requirements.....                                     | 18        |
| Physical specifications.....                                | 19        |
| Clearance requirements.....                                 | 19        |
| Environmental conditions.....                               | 19        |
| Altitude specifications and atmospheric pressure.....       | 20        |
| <b>Appendix A: PCL support</b> .....                        | <b>21</b> |
| PCL emulation commands.....                                 | 21        |
| GL/2 commands.....  | 27        |

|  |            |
|--|------------|
| <b>Appendix B: PjL support.....</b>                          | <b>31</b>  |
| Common variables for both printer languages.....             | 31         |
| Printer-unique PjL variables for both printer languages..... | 33         |
| Common variables for PCL emulation.....                      | 43         |
| Printer-unique variables for PCL emulation.....              | 43         |
| Common variables for PostScript emulation.....               | 44         |
| Printer-unique variables for PostScript emulation.....       | 44         |
| Printer-unique LRESOURCE variables.....                      | 44         |
| Status Readback commands.....                                | 45         |
| USTATUS unsolicited status variables.....                    | 45         |
| PjL messages for auto-continuable conditions.....            | 46         |
| PjL messages for attendance conditions.....                  | 52         |
| PjL messages for paper handling.....                         | 67         |
| PjL messages for paper jams.....                             | 70         |
| Service errors.....  | 76         |
| Device attendance messages.....                              | 77         |
| Lexmark-unique PjL commands.....                             | 77         |
| File and device protection commands.....                     | 78         |
| <b>Appendix C: PostScript support.....</b>                   | <b>79</b>  |
| Supplemental operators.....                                  | 79         |
| Page device parameters.....                                  | 82         |
| User interpreter parameters.....                             | 87         |
| System interpreter parameters.....                           | 88         |
| Devices supported.....                                       | 90         |
| Device parameters.....                                       | 93         |
| PostScript message keys commands.....                        | 102        |
| <b>Index.....</b>  | <b>103</b> |

# Introduction

## Overview

This edition of the *Technical Reference* contains information about the following printers:

X264dn  
X363dn  
X364dn/dw  
X463de  
X464de  
X466dte/dwe

## Understanding letters after model numbers

Some Lexmark printers may have one or more letters after the model name to indicate printer features:

| Acronym | Meaning   |
|---------|---|
| d       | duplex <sup>1</sup>                             |
| e       | e-Task (electronic task) touch-screen interface |
| f       | finisher/stapler                                |
| h       | high-capacity drawer                            |
| m       | mailbox   |
| n       | network   |
| t       | additional tray <sup>2</sup>                    |
| tt      | tandem tray module                              |
| w       | wireless  |

<sup>1</sup> Duplex printing (two-sided printing) accomplished by means of an optional duplex unit or an internal duplex unit based on the product.

<sup>2</sup> The additional tray is part of a drawer.

# Learning about the printer

## Finding information about the printer

### Setup information

| Description   | Where to find   |
|---|---|
| The <i>Setup</i> information gives you instructions for setting up the printer. Follow the set of instructions for local, network, or wireless, depending on what you need. | You can find the <i>Setup</i> information on the inside of the printer box or on the Lexmark Web site at <b>www.lexmark.com</b> . |

### Help

| Description   | Where to find  |
|---|--|
| The Help gives you instructions for using the software. | While in any Lexmark software program, click <b>Help, Tips → Help</b> , or <b>Help → Help Topics</b> . |

### Customer support

| Description              | Where to find (North America)   | Where to find (rest of world)   |
|--------------------------|---|---|
| <b>Telephone support</b> | <p>Call us at</p> <ul style="list-style-type: none"><li>• US: 1-800-332-4120<br/>Monday–Friday (8:00 AM–11:00 PM ET)<br/>Saturday (Noon–6:00 PM ET)</li><li>• Canada: 1-800-539-6275<br/>Monday–Friday (8:00 AM–11:00 PM ET)<br/>Saturday (Noon–6:00 PM ET)</li><li>• Mexico: 001-888-377-0063<br/>Monday–Friday (8:00 AM–8:00 PM ET)</li></ul> <p><b>Note:</b> Telephone numbers and support times may change without notice. For the most recent telephone numbers available, see the printed warranty statement that came with your printer.</p> | <p>Telephone numbers and support hours vary by country or region.</p> <p>Visit our Web site at <b>www.lexmark.com</b>. Select a country or region, and then select the Customer Support link.</p> <p><b>Note:</b> For additional information about contacting Lexmark, see the printed warranty that came with your printer.</p>                          |
| <b>E-mail support</b>    | <p>For e-mail support, visit our Web site: <b>www.lexmark.com</b>.</p> <ol style="list-style-type: none"><li>1 Click <b>SUPPORT</b>.</li><li>2 Click <b>Technical Support</b>.</li><li>3 Select your printer type.</li><li>4 Select your printer model.</li><li>5 From the Support Tools section, click <b>e-Mail Support</b>.</li><li>6 Complete the form, and then click <b>Submit Request</b>.</li></ol>   | <p>E-mail support varies by country or region, and may not be available in some instances.</p> <p>Visit our Web site at <b>www.lexmark.com</b>. Select a country or region, and then select the Customer Support link.</p> <p><b>Note:</b> For additional information about contacting Lexmark, see the printed warranty that came with your printer.</p> |


# Printer Control Language (PCL) page formatting

For more information on PCL, refer to the *Printer Languages and Interfaces Technical Reference*. It contains a complete listing with descriptions of PCL commands.

To determine which PCL commands your printer supports, see “Appendix A: PCL support” on page 21.

## Printable areas

The printable areas and logical pages for PCL emulation (both portrait and landscape orientation) are illustrated below. See the legend that follows for definitions of areas **A** through **I**.



| Legend:  |  |
|----------|--|
| <b>A</b> | Portrait physical page width and landscape physical page length  |
| <b>B</b> | Portrait physical page length and landscape physical page width  |
| <b>C</b> | Portrait logical page width  |
| <b>D</b> | Landscape logical page width   |
| <b>E</b> | Distance between the side edge of the physical page and the logical page in portrait   |
| <b>F</b> | Distance between the side edge of the physical page and the logical page in landscape  |
| <b>G</b> | Distance between the top and bottom edge of the physical page and logical page   |
| <b>H</b> | Distance between the left and right edge of the physical page and the printable area in portrait, or distance between the top and bottom edge of the physical page and printable area in landscape |

**Legend:**

|          |  |
|----------|--|
| <b>I</b> | Distance between the top and bottom edge of the physical page and the printable area in portrait, or distance between the left and right edge of the physical page and the printable area in landscape |
|----------|--|

**Note:** The tables that follow in this chapter list the page sizes and dimensions of each area labeled on the preceding diagram for all paper and envelope sizes your printer supports.

## Supported paper and envelope dimensions

The following table lists the page sizes and print area dimensions for all supported paper and envelope sizes. For more information about the printable areas and logical pages for PCL emulation, see “Printable areas” on page 7.

| Selection                         |                          | Paper/envelope dimensions |             | Dimensions by area (pels) <sup>1</sup> |      |      |      |     |     |   |     |     |
|-----------------------------------|--------------------------|---------------------------|-------------|--|------|------|------|-----|-----|---|-----|-----|
| Page size parameters <sup>2</sup> | Name                     | mm                        | inches      | A                                      | B    | C    | D    | E   | F   | G | H   | I   |
| <b>Paper</b>                      |                          |                           |             |  |      |      |      |     |     |   |     |     |
| 2,602                             | Letter                   | 216 x 279                 | 8.5 x 11    | 5100                                   | 6600 | 4800 | 6360 | 150 | 120 | 0 | 100 | 100 |
| 3,603                             | Legal                    | 216 x 356                 | 8.5 x 14    | 5100                                   | 8400 | 8400 | 8160 | 150 | 120 | 0 | 100 | 100 |
| 12,45,612                         | JIS B5                   | 182 x 257                 | 7.2 x 10.1  | 4300                                   | 6070 | 4000 | 5830 | 150 | 120 | 0 | 100 | 100 |
| 26,626                            | A4 (198 mm) <sup>3</sup> | 210 x 297                 | 8.3 x 11.7  | 4960                                   | 7014 | 4676 | 6778 | 142 | 118 | 0 | 80  | 100 |
| 26,626                            | A4 (203 mm) <sup>3</sup> | 210 x 297                 | 8.3 x 11.7  | 4960                                   | 7014 | 4676 | 6778 | 142 | 118 | 0 | 80  | 100 |
| 1,601                             | Exec                     | 184 x 267                 | 7.25 x 10.5 | 4350                                   | 6300 | 4050 | 6060 | 150 | 120 | 0 | 100 | 100 |
| 13,613                            | A5                       | 148 x 210                 | 5.83 x 8.27 | 3496                                   | 4960 | 3196 | 4720 | 142 | 118 | 0 | 100 | 100 |
| 300                               | Oficio (Mexico)          | 216 x 340                 | 8.5 x 13.4  | 5100                                   | 8040 | 4800 | 7800 | 150 | 120 | 0 | 100 | 100 |

<sup>1</sup> Pel dimensions are for 600 dpi.

<sup>2</sup> Page Size Parameters are explained in the Page Control table in the PCL chapter in the *Printer Language and Interfaces Technical Reference*.

<sup>3</sup> The width of the logical page for A4 paper can be changed from the printer control panel or your software application.

<sup>4</sup> For the Universal paper size, the area dimensions are listed in pel ranges.

<sup>5</sup> Paper ID 99 will be supported for backward compatibility with other Lexmark printers. Paper ID 99 has the same logical paper size as ID 100 (compatible with HP LaserJet 5Si/5SiMx) but is 8 pels wider than the Lexmark 4039.

**Note:** The explanation of the printable area assumes the Print Area menu item is set to Normal. For more information, see “Print Area Menu Item” in the PCL chapter in the *Printer Language and Interfaces Technical Reference*.



| Selection                         |                 | Paper/envelope dimensions |               | Dimensions by area (pels) <sup>1</sup> |                        |                        |                        |     |     |   |     |     |
|-----------------------------------|-----------------|---------------------------|---------------|--|------------------------|------------------------|------------------------|-----|-----|---|-----|-----|
| Page size parameters <sup>2</sup> | Name            | mm                        | inches        | A                                      | B                      | C                      | D                      | E   | F   | G | H   | I   |
| 4 or 10                           | Folio           | 216 x 330                 | 8.5 x 13      | 5100                                   | 7800                   | 4800                   | 7560                   | 150 | 120 | 0 | 100 | 100 |
| 15                                | Statement       | 139.7 x 215.9             | 5.5 x 8.5     | 3300                                   | 5100                   | 3000                   | 4860                   | 150 | 120 | 0 | 100 | 100 |
| 24                                | A6              | 148 x 105                 | 5.8 x 4.1     | 2480                                   | 3496                   | 2199                   | 3260                   | 142 | 118 | 0 | 100 | 100 |
| 101                               | Universal       | 216 x 356                 | 8.5 x 14      | 1800-5100 <sup>4</sup>                 | 1800-8502 <sup>4</sup> | 1500-4800 <sup>4</sup> | 1500-8262 <sup>4</sup> | 150 | 120 | 0 | 100 | 100 |
| <b>Envelope</b>                   |                 |                           |               |  |                        |                        |                        |     |     |   |     |     |
| 90                                | DL              | 220 x 110                 | 8.66 x 4.33   | 2598                                   | 5196                   | 2314                   | 4960                   | 142 | 118 | 0 | 100 | 100 |
| 91                                | C5              | 229 x 162                 | 9.02 x 6.38   | 3826                                   | 5408                   | 3542                   | 5172                   | 142 | 118 | 0 | 100 | 100 |
| 99 <sup>5</sup> , 100             | B5 Envelope     | 250 x 176                 | 9.84 x 6.93   | 4156                                   | 5904                   | 3872                   | 5668                   | 142 | 118 | 0 | 100 | 100 |
| 600                               | Other Envelope  | 216 x 356                 | 8.5 x 14      | 5100                                   | 8400                   | 4800                   | 8160                   | 150 | 120 | 0 | 100 | 100 |
| 89                                | 9 (Com 9)       | 225 x 98                  | 8.875 x 3.875 | 2324                                   | 5324                   | 2024                   | 5084                   | 150 | 120 | 0 | 100 | 100 |
| 81                                | 10 (Com 10)     | 241 x 105                 | 9.5 x 4.125   | 2474                                   | 5700                   | 2174                   | 5460                   | 150 | 120 | 0 | 100 | 100 |
| 80                                | 7 3/4 (Monarch) | 98 x 191                  | 3.875 x 7.5   | 2324                                   | 4500                   | 2024                   | 4260                   | 150 | 120 | 0 | 100 | 100 |

<sup>1</sup> Pel dimensions are for 600 dpi.

<sup>2</sup> Page Size Parameters are explained in the Page Control table in the PCL chapter in the *Printer Language and Interfaces Technical Reference*.

<sup>3</sup> The width of the logical page for A4 paper can be changed from the printer control panel or your software application.

<sup>4</sup> For the Universal paper size, the area dimensions are listed in pel ranges.

<sup>5</sup> Paper ID 99 will be supported for backward compatibility with other Lexmark printers. Paper ID 99 has the same logical paper size as ID 100 (compatible with HP LaserJet 5Si/5SiMx) but is 8 pels wider than the Lexmark 4039.

**Note:** The explanation of the printable area assumes the Print Area menu item is set to Normal. For more information, see "Print Area Menu Item" in the PCL chapter in the *Printer Language and Interfaces Technical Reference*.

# Printer Job Language (PJM)

## PJM commands information

Your printer supports complete PJL commands, including certain commands that cause the printer to enter PCL emulation, PostScript emulation, and Personal Printer Data Stream (PPDS).

For a complete listing with descriptions of PJL commands, see the *Printer Languages and Interfaces Technical Reference*.

To determine which commands your printer supports, see "Appendix B: PJL support" on page 31.

# PostScript (PS) emulation

Your printer supports complete PostScript emulation supplemental operators. For full descriptions in detail for these operators, refer to the PostScript emulation chapter in the Printer Languages and Interfaces Technical Reference.

To determine which commands your printer supports, see “Appendix C: PostScript support” on page 79.

## Paper sizes supported

| ✓ = Supported<br>X = Not supported<br>Paper sizes |                |               |               |   | Printer models                    |  |
|---|----------------|---------------|---------------|---|-----------------------------------|--|
| Size  | Literal name   | Size (mm)     | Size (inches) | Size (points)   | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de, X466dte,<br>X466dwe |
| Letter  | letter         | 215.9 x 279.4 | 8.5 x 11.0    | 612 x 792   | ✓                                 | ✓  |
| Legal   | legal          | 215.9 x 355.6 | 8.5 x 14.0    | 612 x 1008  | ✓                                 | ✓  |
| JIS B5  | b5*            | 182.0 x 257.0 | 7.2 x 10.1    | 516 x 729   | ✓                                 | ✓  |
| A4  | a4             | 210.0 x 297.0 | 8.3 x 11.7    | 595 x 842   | ✓                                 | ✓  |
| Executive   | executive page | 184.2 x 266.7 | 7.25 x 10.5   | 522 x 756   | ✓                                 | ✓  |
| A5  | a5             | 148.0 x 210.0 | 5.83 x 8.27   | 419 x 595   | ✓                                 | ✓  |
| Oficio  | oficio         | 215.9 x 340.4 | 8.5 x 13.4    | 612 x 965 (Lexmark<br>unique size)<br>612 x 972 (official<br>PostScript size) | ✓                                 | ✓  |
| Folio   | folio          | 215.9 x 330.2 | 8.5 x 13.0    | 612 x 936   | ✓                                 | ✓  |
| Statement   | statement      | 139.7 x 215.9 | 5.5 x 8.5     | 396 x 612   | ✓                                 | ✓  |
| A6  | a6             | 105.0 x 148.0 | 4.13 x 5.83   | 297 x 419   | ✓                                 | ✓  |
| Universal   | universal      | 216 x 356     | 8.5 x 14      | 612 x 1008  | ✓                                 | ✓  |

\* This is a Japanese Industry Standard (JIS) paper size. The same named designation is used by JIS and International Standards Organization (ISO) for different paper sizes.

# PostScript paper tray support

When the printer receives one of the operators listed in “Tray selected with tray operators” on page 12, it performs the actions listed as follows. This paper tray selection process ends as soon as a suitable paper source is chosen and paper is fed from this tray.

- The printer checks the value of **manualfeed** in **statusdict** and the ManualFeed page device parameter. If either one is true, the printer sends a message to load the requested size in the manual feed tray or multipurpose feeder.
- The PageSize Policy is set to 0 by means of **setpagedevice**.
- The printer checks the paper size loaded in the current active source to determine if it matches the requested size. If the sizes match, the paper is fed from the active source.

**Note:** The current active tray is the last source that was selected from the printer control panel or by the printer language.

- If the requested size and the size loaded in the active source do not match, the sources are searched in the order defined by the Priority array in the InputAttributes dictionary in the pagedevice dictionary.
- If the requested media size is not found by the previous search, the following search order is used:
  - Tray 1
  - Tray 2
  - Tray 3
  - Multipurpose Feeder
  - Tray 4
  - Tray 5
- If the requested size cannot be located in any automatic source, a **configurationerror** is issued and the job is flushed.

For printers that support automatic duplexing:

- Automatic duplexing is not supported for custom-size paper or for envelopes in the multipurpose feeder. Automatic duplexing is supported from the multipurpose feeder for all other papers.
- If the paper source is changed before the back side of a duplexed page prints, a blank back page prints, the paper source changes, and the information for the back side of the page is printed on the front side of a page sent from the new paper source.

When these operators are used, it is equivalent to executing the following PostScript emulation sequence:

```
<< /PageSize [x y]/ImagingBBox null /Policies << /PageSize 0>> >>
setpagedevice
```

where *x y* are the PageSize in points.

## Tray selected with tray operators

| ✓ = Supported<br>X = Not supported |   | Printer models                 |  |
|------------------------------------|---|--------------------------------|--|
| Operator                           | Tray selected (corresponding image size is set) | X264dn, X363dn, X364dn, X364dw | X463de, X464de, X466de, X466dte, X466dwe |
| 11x17tray                          | tray with 279.4 x 431.8-mm (11 x 17-in.) paper  | X                              | X  |
| a3tray                             | tray with A3-size paper                         | X                              | X  |

| ✓ = Supported<br>X = Not supported |   | Printer models                 |  |
|------------------------------------|---|--------------------------------|--|
| Operator                           | Tray selected (corresponding image size is set)                           | X264dn, X363dn, X364dn, X364dw | X463de, X464de, X466de, X466dte, X466dwe |
| a4tray                             | tray with A4-size paper   | ✓                              | ✓  |
| a5tray                             | tray with A5-size paper   | ✓                              | ✓  |
| a6tray                             | tray with A6-size paper   | ✓                              | ✓  |
| b4tray                             | tray with JIS B4-size paper   | X                              | X  |
| b5tray                             | tray with B5-size paper   | ✓                              | ✓  |
| customtray                         | tray with custom-size paper   | X                              | X  |
| executivetray                      | tray with executive-size paper  | ✓                              | ✓  |
| foliotray                          | tray with folio-size paper  | ✓                              | ✓  |
| ledgertray                         | tray with 279.4 x 431.8-mm (11 x 17-in.) paper with landscape orientation | X                              | X  |
| legaltray                          | tray with legal-size paper  | ✓                              | ✓  |
| lettertray                         | tray with letter-size paper   | ✓                              | ✓  |
| oficiotray                         | tray with oficio-size paper   | ✓                              | ✓  |
| statementtray                      | tray with statement-size paper  | ✓                              | ✓  |

# PostScript envelope size support

The literal names in “Envelope sizes supported” on page 14 are also supported as operators in **userdict**. These operators change the image size, but do not change the active paper source. Therefore, when these operators are used, part of the image may be clipped.

When these literal names are used as operators, it is equivalent to executing the following PostScript emulation sequence. The following example uses a 3.875 x 7.5 envelope.

```
<</Policies <</PageSize 7>> /PageSize [279 540]>> >>setpagedevice
```

## Envelope sizes supported

| ✓ = Supported<br>X = Not supported<br>Envelope sizes |                     |                 |               |               | Printer models                          |  |
|--|---------------------|-----------------|---------------|---------------|---|--|
| Size name  | Literal name        | Size (mm)       | Size (inches) | Size (points) | X264dn,<br>X363dn,<br>X364dn,<br>X364dw | X463de,<br>X464de,<br>X466de,<br>X466dte,<br>X466dwe |
| 7 3/4  | 3.875x7.5envelope   | 98.4 x 190.5    | 3.875 x 7.5   | 279 x 540     | ✓                                       | ✓  |
| Commercial 9   | 3.875x8.875envelope | 98.4 x 225.4    | 3.875 x 8.875 | 279 x 639     | ✓                                       | ✓  |
| Commercial 10  | 4.125x9.5envelope   | 104.8 x 241.3   | 4.125 x 9.5   | 297 x 684     | ✓                                       | ✓  |
| International DL                                     | 110x220envelope     | 110 x 220       | 4.33 x 8.66   | 312 x 624     | ✓                                       | ✓  |
| International C5                                     | 162x229envelope     | 162 x 229       | 6.38 x 9.01   | 459 x 649     | ✓                                       | ✓  |
| International B5                                     | 176x250envelope     | 176 x 250       | 6.93 x 9.84   | 499 x 708     | ✓                                       | ✓  |
| Other envelope                                       | otherenvelope       | 229.11 x 355.6  | 9.02 x 14     | 612 x 996     | ✓                                       | ✓  |
| otherenvelope*                                       | Other               | 296.93 x 427.48 | 11.69 x 16.83 | 841 x 842     | X                                       | X  |

\* For other envelopes, the page is formatted to 216 x 356 mm (8.5 x 14 in.) unless a size is specified by your software program.

## Literal names supported

| ✓ = Supported<br>X = Not Supported<br>Literal names |                         | Printer models                    |   |
|---|-------------------------|-----------------------------------|---|
| Literal name  | Compatible literal name | X264dn, X363dn, X364dn,<br>X364dw | X463de, X464de, X466de,<br>X466dte, X466dwe |
| monarchenvelope                                     | 3.875x7.5envelope       | ✓                                 | ✓   |
| com10envelope                                       | 4.125x9.5envelope       | ✓                                 | ✓   |
| dlenvelope  | 110x220envelope         | ✓                                 | ✓   |

| ✓ = Supported<br>X = Not Supported<br>Literal names |                         | Printer models                    |   |
|---|-------------------------|-----------------------------------|---|
| Literal name  | Compatible literal name | X264dn, X363dn, X364dn,<br>X364dw | X463de, X464de, X466de,<br>X466dte, X466dwe |
| c5envelope  | 162x229envelope         | ✓                                 | ✓   |
| b5envelope  | 176x250envelope         | ✓                                 | ✓   |

## PostScript envelope tray support

If **manualfeed** in **statusdict** and the ManualFeed page device parameter are false when the printer receives one of the envelopetray operators listed in “Envelopetray operator selections” on page 15, then the printer:

- Sets the PageSize Policy to 0.
- Checks the active source to see if it matches the requested envelope size. If the sizes match, the envelope is fed from the active source.

**Note:** The active source is the last source selected from the printer control panel or data stream.

- If the requested size and the size loaded in the active source do not match, the sources are searched in the order defined by the Priority array in the InputAttributes dictionary in the pagedevice dictionary.
- If the requested media size is not found by the previous search, the following search order is used:
  - Envelope Feeder
  - Multipurpose Feeder
- If the requested size and type are not available from any automatic source, you are prompted to load the requested envelope size and type in the manual feed source.
- If the size is still not available, a **configurationerror** is issued and the print job is flushed.

If manualfeed or ManualFeed is true, the printer prompts you to load the requested size manually. If no manual feed exists on the printer, a **rangecheck** error message is generated

The envelope tray the printer selects when it receives an **envelopetray** operator is listed in “Envelopetray operator selections” on page 15. These operators are equivalent to executing the following PostScript emulation sequence:

```
<</PageSize [x y] /ImagingBBox null /Policies<</PageSize 0>> >>
setpagedevice
```

where **xy** are the PageSize in points.

### Envelopetray operator selections

| ✓ = Supported<br>X = Not supported<br>Tray operators |   | Printer models                    |   |
|--|---|-----------------------------------|---|
| Operator   | Tray selected (Corresponding image size is set) | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de, X466de,<br>X466dte, X466dwe |
| 110x220envelopetray                                  | tray with 110 x 220 size envelopes              | ✓                                 | ✓   |
| dlenvelopetray                                       | tray with 110 x 220 size envelopes              | ✓                                 | ✓   |

PostScript (PS) emulation

| ✓ = Supported<br>X = Not supported<br>Tray operators |   | Printer models                 |  |
|--|---|--------------------------------|--|
| Operator   | Tray selected (Corresponding image size is set) | X264dn, X363dn, X364dn, X364dw | X463de, X464de, X466de, X466dte, X466dwe |
| 162x229envelopetray                                  | tray with 162 x 229 size envelopes              | ✓                              | ✓  |
| c5envelopetray                                       | tray with 162 x 229 size envelopes              | ✓                              | ✓  |
| 176x250envelopetray                                  | tray with 176 x 250 size envelopes              | ✓                              | ✓  |
| b5envelopetray                                       | tray with 176 x 250 size envelopes              | ✓                              | ✓  |
| 3.875x7.5envelopetray                                | tray with 3.875 x 7.5 size envelopes            | ✓                              | ✓  |
| monarcenvelopetray                                   | tray with 3.875 x 7.5 size envelopes            | ✓                              | ✓  |
| 3.875x8.875envelopetray                              | tray with 3.875 x 8.875 size envelopes          | ✓                              | ✓  |
| 4.125x9.5envelopetray                                | tray with 4.125 x 9.5 size envelopes            | ✓                              | ✓  |
| com10envelopetray                                    | tray with 4.125 x 9.5 size envelopes            | ✓                              | ✓  |
| otherenvelopetray                                    | tray with other size envelopes                  | ✓                              | ✓  |



# Printer specifications

This chapter lists printer specifications and information about hardware, environmental conditions, and power requirements.

## Airflow requirement

The room should meet ASHRAE 62—1989 standards.

## Noise emission levels

The following measurements were made in accordance with ISO 7779 and reported in conformance with ISO 9296.

| Status  | 1-meter average sound pressure, dBA |  |
|---|-------------------------------------|--|
|   | X264dn, X363dn, X364dn, X364dw      | X463de, X464de, X466de, X466dte, X466dwe |
| Printing  | 54                                  | 53                                       |
| Scanning  | 51                                  | 49                                       |
| Copying   | 54                                  | 53                                       |
| Quiet Mode printing   | 49                                  | Not applicable                           |
| Standby (Idle without Power Saver)  | 27                                  | 22                                       |
| <b>Note:</b> Measurements apply to 300-dpi, 600-dpi, and 1200-dpi printing. |                                     |  |

| Status  | Declared sound power level, Bels |  |
|---|----------------------------------|--|
|   | X264dn, X363dn, X364dn, X364dw   | X463de, X464de, X466de, X466dte, X466dwe |
| Printing  | 6.7                              | 6.8                                      |
| Scanning  | 6.6                              | 6.5                                      |
| Copying   | 6.7                              | 6.8                                      |
| Quiet Mode printing   | 6.4                              | Not applicable                           |
| Standby (Idle without Power Saver)  | 4.1                              | 3.7                                      |
| <b>Note:</b> Measurements apply to 300-dpi, 600-dpi, and 1200-dpi printing. |                                  |  |

# Electrical specifications

| Printer model  | Electrical specification  |
|--|---|
| X264 MFP low voltage models*   | 100-110 V (Japan) at 50-60 Hz, nominal<br>100-127 V at 50-60 Hz, nominal<br>90-110 V (Japan), extreme<br>90 -135 V, extreme |
| X264 MFP high voltage models   | 198-254 V, extreme<br>220-240 V at 50-60 Hz, nominal  |
| X360 MFP low voltage models  | 100-110 V (Japan) at 50-60 Hz, nominal<br>100-127 V at 50-60 Hz, nominal<br>90-110 V (Japan), extreme<br>90 -135 V, extreme |
| X360 MFP high voltage models   | 198-254 V, extreme<br>220-240 V at 50-60 Hz, nominal  |
| X460 MFP low voltage models  | 90-137 V, extreme<br>100-127 V at 50-60 Hz, nominal   |
| X460 MFP high voltage models   | 198-259 V, extreme<br>220-240 V at 50-60 Hz, nominal (not available in all countries)                                       |
| * Using a 220–110 power converter with 110 V printer is not recommended. |   |

**Warning—Potential Damage:** Lexmark recommends that you do not use voltage converters with printers.

## Power requirements

This lists the nominal average power requirements (including fuser power).

| Printing states                                  | X264 MFP | X360 MFP | X460 MFP |
|--|----------|----------|----------|
| <b>Average power while printing continuously</b> |          |          |          |
| 1-sided (simplex)                                | 440 W    | 480 W    | 540 W    |
| 2-sided (duplex)                                 | 275 W    | 300 W    | 340 W    |
| <b>Average power while idle</b>                  |          |          |          |
| Power Saver on                                   | 14 W     | 16 W     | 25 W     |
| Ready mode                                       | 20 W     | 22 W     | 45 W     |
| <b>Max current while printing</b>                |          |          |          |
| 100 V  | 8.6 A    | 8.6 A    | 8.6 A    |
| 120 V  | 7.6 A    | 7.6 A    | 7.6 A    |
| 230 V  | 3.7 A    | 3.7 A    | 3.7 A    |
| Copying continuously                             | 440 W    | 440 W    | 560 W    |
| Scanning continuously                            | 29 W     | 32 W     | 55 W     |

# Physical specifications

## Lexmark X264, X360, X460 dimensions

|                       | Height            | Width             | Depth             | Weight          |
|-----------------------|-------------------|-------------------|-------------------|-----------------|
| X264 MFP base printer | 440 mm (17.3 in.) | 428 mm (16.8 in.) | 405 mm (16 in.)   | 19.5 kg (43 lb) |
| X360 MFP base printer | 471 mm (18.5 in.) | 428 mm (16.8 in.) | 405 mm (16 in.)   | 20 kg (44 lb)   |
| X460 MFP base printer | 546 mm (21.5 in.) | 488 mm (19.2 in.) | 438 mm (17.2 in.) | 22.7 kg (50 lb) |

## Input options for Lexmark X264, X360, X460

| Option name      | Height              | Width              | Depth              | Weight           |
|------------------|---------------------|--------------------|--------------------|------------------|
| 250-sheet drawer | 89 mm (3.5 in.)     | 406 mm (15.98 in.) | 367 mm (14.45 in.) | 2.55 kg (5.6 lb) |
| 550-sheet drawer | 130.5 mm (5.08 in.) | 406 mm (15.98 in.) | 387 mm (15.24 in.) | 3.23 kg (7.2 lb) |

# Clearance requirements

## Lexmark X264, X360, X460

| Model    | Left side        | Right side       | Front            | Rear               | Top             |
|----------|------------------|------------------|------------------|--------------------|-----------------|
| X264 MFP | 203.2 mm (8 in.) | 76.19 mm (3 in.) | 203.2 mm (8 in.) | 304.79 mm (12 in.) | 254 mm (10 in.) |
| X360 MFP | 203.2 mm (8 in.) | 76.19 mm (3 in.) | 203.2 mm (8 in.) | 304.79 mm (12 in.) | 254 mm (10 in.) |
| X460 MFP | 76.19 mm (3 in.) | 203.2 mm (8 in.) | 203.2 mm (8 in.) | 304.79 mm (12 in.) | 254 mm (10 in.) |

# Environmental conditions

**Note:** When shipping or storing printers, always pack the printer supplies (cartridges and photoconductors, for example) separately.

## Air temperature ranges

| Printer model                            | Operating value           | Shipping value            | Storage (unpacked)      |
|--|---------------------------|---------------------------|-------------------------|
| X264dn, X363dn, X364dn, X364dw           | 15.6 to 32.2°C (60- 90°F) | -20 to 40°C (-4 to 104°F) | 0 to 40°C (32 to 104°F) |
| X463de, X464de, X466de, X466dte, X466dwe | 15.6 to 32.2°C (60- 90°F) | -20 to 40°C (-4 to 104°F) | 0 to 40°C (32 to 104°F) |

## Humidity ranges

| Printer model                            | Operating value | Shipping value | Storage value |
|--|-----------------|----------------|---------------|
| X264dn, X363dn, X364dn, X364dw           | 8%-80%          | 8%-95%         | 8%-80%        |
| X463de, X464de, X466de, X466dte, X466dwe | 8%-80%          | 8%-95%         | 8%-80%        |

# Altitude specifications and atmospheric pressure

## Altitude specifications

| Printer model                               | Altitude (above sea level) |  |
|---|----------------------------|--|
|   | Operating                  | Shipping/storage   |
| X264dn, X363dn, X364dn, X364dw              | 0 to 2500 M (8, 200 ft.)   | 0.25 atmospheric pressure ( equal to 10,300 M)<br>[34,000 ft.] |
| X463de, X464de, X466de, X466dte,<br>X466dwe | 0 to 2500 M (8, 200 ft.)   | 0.25 atmospheric pressure ( equal to 10,300 M)<br>[34,000 ft.] |

## Atmospheric Pressure

74.6 kPa

# Appendix A: PCL support

## PCL emulation commands

| ✓ = Supported<br>X = Not supported |   | Printer model                     |  |
|------------------------------------|---|-----------------------------------|--|
| Command                            | Function                                      | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de, X466dte,<br>X466dwe |
| Decimal 8                          | BS, Backspace                                 | ✓                                 | ✓  |
| Decimal 9                          | HT, Horizontal Tab                            | ✓                                 | ✓  |
| Decimal 10                         | LF, Line Feed                                 | ✓                                 | ✓  |
| Decimal 12                         | FF, Form Feed                                 | ✓                                 | ✓  |
| Decimal 13                         | CR, Carrier Return                            | ✓                                 | ✓  |
| Decimal 14                         | SO, Select Secondary Font                     | ✓                                 | ✓  |
| Decimal 15                         | SI, Select Primary Font                       | ✓                                 | ✓  |
| Decimal 32                         | SP, Space                                     | ✓                                 | ✓  |
| ESC $\text{E}$                     | Printer Reset                                 | ✓                                 | ✓  |
| ESC $\text{Y}$                     | Display Functions-On                          | ✓                                 | ✓  |
| ESC $\text{Z}$                     | Display Functions-Off                         | ✓                                 | ✓  |
| ESC $\text{z}$                     | Print Test Page                               | X                                 | X  |
| ESC $\&\text{a}\#\text{C}$         | Horizontal Cursor Position<br>(in Columns)    | ✓                                 | ✓  |
| ESC $\&\text{a}\#\text{G}$         | Duplex Page Side Selection                    | ✓                                 | ✓  |
| ESC $\&\text{a}\#\text{H}$         | Horizontal Cursor Position<br>(in Decipoints) | ✓                                 | ✓  |
| ESC $\&\text{a}\#\text{L}$         | Set Left Margin                               | ✓                                 | ✓  |
| ESC $\&\text{a}\#\text{M}$         | Set Right Margin                              | ✓                                 | ✓  |
| ESC $\&\text{a}\#\text{N}$         | Negative Motion                               | X                                 | X  |
| ESC $\&\text{a}\#\text{P}$         | Print Direction                               | ✓                                 | ✓  |
| ESC $\&\text{a}\#\text{R}$         | Vertical Cursor Position (in Rows)            | ✓                                 | ✓  |
| ESC $\&\text{a}\#\text{V}$         | Vertical Cursor Position<br>(in Decipoints)   | ✓                                 | ✓  |

| ✓ = Supported<br>X = Not supported |                                    | Printer model                     |  |
|------------------------------------|------------------------------------|-----------------------------------|--|
| Command                            | Function                           | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de, X466dte,<br>X466dwe |
| ESC&b#M                            | Monochrome Print Mode              | ✓                                 | ✓  |
| ESC&b#W[data]                      | Configuration Command              | X                                 | X  |
| ESC&c#T                            | Character Text Path Direction      | ✓                                 | ✓  |
| ESC&d@                             | Underline-Disable                  | ✓                                 | ✓  |
| ESC&d#A                            | Number of Collated Copies          | ✓                                 | ✓  |
| ESC&d#D                            | Underline-Enable                   | ✓                                 | ✓  |
| ESC&f#F                            | Set Universal Height               | ✓                                 | ✓  |
| ESC&f#G                            | Set Universal Width                | ✓                                 | ✓  |
| ESC&f#O                            | Set Universal Feed Direction       | ✓                                 | ✓  |
| ESC&f#W                            | Set Universal Custom Name          | ✓                                 | ✓  |
| ESC&f#S                            | Push / Pop Cursor Position         | ✓                                 | ✓  |
| ESC&f#X                            | Macro Control                      | ✓                                 | ✓  |
| ESC&f#Y                            | Set Macro ID                       | ✓                                 | ✓  |
| ESC&k#G                            | Set Line Termination               | ✓                                 | ✓  |
| ESC&k#H                            | Set Horizontal Motion Index        | ✓                                 | ✓  |
| ESC&k#S                            | Select Primary and Secondary Pitch | ✓                                 | ✓  |
| ESC&k#W                            | Text Scale Mode                    | X                                 | X  |
| ESC&l#A                            | Set Page Size                      | ✓                                 | ✓  |
| ESC&l#C                            | Set Vertical Motion Index          | ✓                                 | ✓  |
| ESC&l#D                            | Set Line Spacing                   | ✓                                 | ✓  |
| ESC&l#E                            | Set Top Margin                     | ✓                                 | ✓  |
| ESC&l#F                            | Set Text Length                    | ✓                                 | ✓  |
| ESC&l#G                            | Set Output Bin                     | ✓                                 | ✓  |
| ESC&l#H                            | Paper Source                       | ✓                                 | ✓  |
| ESC&l#L                            | Skip Perforation                   | ✓                                 | ✓  |
| ESC&l#O                            | Select Orientation                 | ✓                                 | ✓  |

## Appendix A: PCL support

| ✓ = Supported<br>X = Not supported |   | Printer model                     |  |
|------------------------------------|---|-----------------------------------|--|
| Command                            | Function                                  | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de, X466dte,<br>X466dwe |
| ESC&l#M(b)                         | Paper Type                                | X                                 | X  |
| ESC&l#P                            | Set Page Length                           | ✓                                 | ✓  |
| ESC&l#S                            | Simplex/Duplex Print                      | ✓                                 | ✓  |
| ESC&l#U                            | Long-Edge Offset Registration             | ✓                                 | ✓  |
| ESC&l#X                            | Number of Copies                          | ✓                                 | ✓  |
| ESC&l#Z                            | Short-Edge Offset Registration            | ✓                                 | ✓  |
| ESC&l1T                            | Job Separation                            | X                                 | X  |
| ESC&n#W [operation] [string id]    | Alphanumeric ID                           | ✓                                 | ✓  |
| ESC&p#C                            | Palette Control                           | ✓                                 | ✓  |
| ESC&p#I                            | Palette Control ID                        | ✓                                 | ✓  |
| ESC&p#S                            | Select Palette                            | ✓                                 | ✓  |
| ESC&p#X[data]                      | Transparent Print Data                    | ✓                                 | ✓  |
| ESC&r#F                            | Flush All Pages                           | ✓                                 | ✓  |
| ESC&s#C                            | End-Of-Line Text Wrap                     | ✓                                 | ✓  |
| ESC&t#P                            | Text Parsing Method                       | ✓                                 | ✓  |
| ESC&u#D                            | Unit of Measure                           | ✓                                 | ✓  |
| ESC(#                              | Primary Font Symbol Set                   | ✓                                 | ✓  |
| ESC(#X                             | Select Primary Download Font (by Font ID) | ✓                                 | ✓  |
| ESC(3@                             | Select Default Primary Font               | ✓                                 | ✓  |
| ESC(f#W[data]                      | Define Symbol Set                         | ✓                                 | ✓  |
| ESC(s#B                            | Primary Font Stroke Weight                | ✓                                 | ✓  |
| ESC(s#H                            | Primary Font Pitch                        | ✓                                 | ✓  |
| ESC(s#P                            | Primary Font Spacing                      | ✓                                 | ✓  |
| ESC(s#S                            | Primary Font Style                        | ✓                                 | ✓  |
| ESC(s#T                            | Primary Font Typeface Selection           | ✓                                 | ✓  |

## Appendix A: PCL support

| ✓ = Supported<br>X = Not supported |   | Printer model                     |  |
|------------------------------------|---|-----------------------------------|--|
| Command                            | Function                                    | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de, X466dte,<br>X466dwe |
| ESC(s#V                            | Primary Font Height (Point Size)            | ✓                                 | ✓  |
| ESC(s#W[data]                      | Load Character                              | ✓                                 | ✓  |
| ESC)#                              | Secondary Font Symbol Set                   | X                                 | X  |
| ESC)#X                             | Select Secondary Download Font (by Font ID) | X                                 | X  |
| ESC)3@                             | Select Default Secondary Font               | ✓                                 | ✓  |
| ESC)s#B                            | Secondary Font Stroke Weight                | X                                 | X  |
| ESC)s#H                            | Secondary Font Pitch                        | X                                 | X  |
| ESC)s#P                            | Secondary Font Spacing                      | X                                 | X  |
| ESC)s#S                            | Secondary Font Style                        | X                                 | X  |
| ESC)s#T                            | Secondary Font Typeface Selection           | X                                 | X  |
| ESC)s#V                            | Secondary Font Height (Point Size)          | X                                 | X  |
| ESC)s#W[data]                      | Load Font Header                            | ✓                                 | ✓  |
| ESC*b#M                            | Set Raster Compression Mode                 | ✓                                 | ✓  |
| ESC*b#V[data]                      | Transfer Raster Data (by Plane)             | ✓                                 | ✓  |
| ESC*b#W[data]                      | Transfer Raster Data (by Row / Block)       | ✓                                 | ✓  |
| ESC*b#Y                            | Y Offset                                    | ✓                                 | ✓  |
| ESC*c#A                            | Horizontal Rectangle Size (in PCL Units)    | ✓                                 | ✓  |
| ESC*c#B                            | Vertical Rectangle Size (in PCL Units)      | ✓                                 | ✓  |
| ESC*c#D                            | Set Font ID                                 | ✓                                 | ✓  |
| ESC*c#E                            | Set Character Code                          | ✓                                 | ✓  |
| ESC*c#F                            | Font Control                                | ✓                                 | ✓  |
| ESC*c#G                            | Area Fill ID                                | ✓                                 | ✓  |
| ESC*c#H                            | Horizontal Rectangle Size (in Decipoints)   | ✓                                 | ✓  |
| ESC*c#K                            | GL/2 Horizontal Plot Size (in Inches)       | ✓                                 | ✓  |
| ESC*c#L                            | GL/2 Vertical Plot Size (in Inches)         | ✓                                 | ✓  |

## Appendix A: PCL support



| ✓ = Supported<br>X = Not supported |  | Printer model                     |  |
|------------------------------------|--|-----------------------------------|--|
|                                    |  | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de, X466dte,<br>X466dwe |
| Command                            | Function   |                                   |  |
| ESC*c#P                            | Fill Rectangular Area                            | ✓                                 | ✓  |
| ESC*c#Q                            | Pattern Control                                  | ✓                                 | ✓  |
| ESC*c#R                            | Symbol Set ID Code                               | ✓                                 | ✓  |
| ESC*c#S                            | Symbol Set Control                               | ✓                                 | ✓  |
| ESC*c0T                            | Set Picture Frame Anchor Point                   | ✓                                 | ✓  |
| ESC*c#V                            | Vertical Rectangle Size<br>(in Decipoints)       | ✓                                 | ✓  |
| ESC*c#W[data]                      | User-Defined Pattern                             | ✓                                 | ✓  |
| ESC*c#X                            | Picture Frame Horizontal Size<br>(in Decipoints) | ✓                                 | ✓  |
| ESC*c#Y                            | Picture Frame Vertical Size<br>(in Decipoints)   | ✓                                 | ✓  |
| ESC*ℓ#O                            | Logical Operation                                | ✓                                 | ✓  |
| ESC*ℓ#R                            | Pixel Placement                                  | ✓                                 | ✓  |
| ESC*ℓ#W[data]                      | Color Lookup Tables                              | X                                 | X  |
| ESC*m#W[data]                      | Download Dither Matrix                           | ✓                                 | ✓  |
| ESC*o#M(b)                         | Print Quality                                    | X                                 | X  |
| ESC*o#Q                            | Mechanical Print Quality                         | X                                 | X  |
| ESC*o#W[data]                      | Driver Configuration Command                     | ✓                                 | ✓  |
| ESC*p#P                            | Push / Pop Palette                               | ✓                                 | ✓  |
| ESC*p#R                            | Set Pattern Reference Point                      | ✓                                 | ✓  |
| ESC*p#X                            | Horizontal Cursor Position<br>(in PCL Units)     | ✓                                 | ✓  |
| ESC*p#Y                            | Vertical Cursor Position<br>(in PCL Units)       | ✓                                 | ✓  |
| ESC*r#A                            | Start Raster Graphics                            | ✓                                 | ✓  |
| ESC*r#F                            | Raster Graphics Presentation Mode                | ✓                                 | ✓  |
| ESC*r#S                            | Raster Width (Source)                            | ✓                                 | ✓  |
| ESC*r#T                            | Raster Height (Source)                           | ✓                                 | ✓  |

## Appendix A: PCL support

| ✓ = Supported<br>X = Not supported |                                   | Printer model                     |  |
|------------------------------------|-----------------------------------|-----------------------------------|--|
| Command                            | Function                          | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de, X466dte,<br>X466dwe |
| ESC*r#U                            | Simple Color                      | ✓                                 | ✓  |
| ESC*rB                             | End Raster Graphics (Version B)   | ✓                                 | ✓  |
| ESC*rC                             | End Raster Graphics (Version C)   | ✓                                 | ✓  |
| ESC*s#I                            | Inquire Status Readback Entity    | ✓                                 | ✓  |
| ESC*s1M                            | Free Space                        | ✓                                 | ✓  |
| ESC*s#T                            | Set Status Readback Location Type | ✓                                 | ✓  |
| ESC*s#U                            | Set Status Readback Location Unit | ✓                                 | ✓  |
| ESC*s#X                            | Echo                              | ✓                                 | ✓  |
| ESC*t#H                            | Raster Width Destination          | ✓                                 | ✓  |
| ESC*t#I                            | Gamma Correction                  | ✓                                 | ✓  |
| ESC*t#J                            | Render Algorithm                  | X                                 | X  |
| ESC*t#K                            | Scale Algorithm                   | X                                 | X  |
| ESC*t#R                            | Raster Resolution                 | ✓                                 | ✓  |
| ESC*t#V                            | Raster Height Destination         | ✓                                 | ✓  |
| ESC*g#W                            | Set Raster Configuration          | X                                 | X  |
| ESC*v#A                            | Color Component One               | ✓                                 | ✓  |
| ESC*v#B                            | Color Component Two               | ✓                                 | ✓  |
| ESC*v#C                            | Color Component Three             | ✓                                 | ✓  |
| ESC*v#I                            | Assign Color Index                | ✓                                 | ✓  |
| ESC*v#N                            | Source Transparency Mode          | ✓                                 | ✓  |
| ESC*v#O                            | Pattern Transparency Mode         | ✓                                 | ✓  |
| ESC*v#S                            | Foreground Color                  | ✓                                 | ✓  |
| ESC*v#T                            | Select Current Pattern            | ✓                                 | ✓  |
| ESC*v#W[data]                      | Configure Image Data              | ✓                                 | ✓  |
| ESC*i#W[data]                      | Viewing Illuminant                | X                                 | X  |
| ESCg                               | Clear Horizontal Margins          | ✓                                 | ✓  |

## Appendix A: PCL support

| ✓ = Supported<br>X = Not supported |  | Printer model                     |  |
|------------------------------------|--|-----------------------------------|--|
| Command                            | Function   | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de, X466dte,<br>X466dwe |
| ESC=                               | Half Line-Feed   | ✓                                 | ✓  |
| ESC%#A                             | Enter PCL Emulation  | ✓                                 | ✓  |
| ESC%#B                             | Enter GL/2 Language<br><b>Note:</b> The values of -1, 2, and 3 are not supported by any of the printers included in this document. | ✓                                 | ✓  |
| ESC% 12345X                        | Universal Exit Language (UEL) / Start of PJJ   | ✓                                 | ✓  |

## GL/2 commands

| ✓ = Supported<br>X = Not supported |                          | Printer model                     |  |
|------------------------------------|--------------------------|-----------------------------------|--|
| Command                            | Function                 | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de, X466dte,<br>X466dwe |
| AA                                 | Arc Absolute             | ✓                                 | ✓  |
| AC                                 | Anchor Corner            | ✓                                 | ✓  |
| AD                                 | Define Alternate Font    | ✓                                 | ✓  |
| AR                                 | Arc Relative             | ✓                                 | ✓  |
| AT                                 | Arc Absolute Three Point | ✓                                 | ✓  |
| BR                                 | Bezier Relative          | ✓                                 | ✓  |
| BZ                                 | Bezier Absolute          | ✓                                 | ✓  |
| CF                                 | Character Fill           | ✓                                 | ✓  |
| CI                                 | Circle                   | ✓                                 | ✓  |
| CO                                 | Comment                  | ✓                                 | ✓  |
| CP                                 | Character Plot           | ✓                                 | ✓  |
| CR                                 | Set Color Range          | ✓                                 | ✓  |
| DF                                 | Default                  | ✓                                 | ✓  |
| DI                                 | Absolute Direction       | ✓                                 | ✓  |

| ✓ = Supported<br>X = Not supported |                                   | Printer model                     |  |
|------------------------------------|-----------------------------------|-----------------------------------|--|
| Command                            | Function                          | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de, X466dte,<br>X466dwe |
| DR                                 | Relative Direction                | ✓                                 | ✓  |
| DT                                 | Define Label Terminator           | ✓                                 | ✓  |
| DV                                 | Define Variable Text Path         | ✓                                 | ✓  |
| EA                                 | Edge Rectangle Absolute           | ✓                                 | ✓  |
| EP                                 | Edge Polygon                      | ✓                                 | ✓  |
| ER                                 | Edge Rectangle Relative           | ✓                                 | ✓  |
| ES                                 | Extra Space                       | ✓                                 | ✓  |
| EW                                 | Edge Wedge                        | ✓                                 | ✓  |
| FI                                 | Primary Font                      | ✓                                 | ✓  |
| FN                                 | Secondary Font                    | ✓                                 | ✓  |
| FP                                 | Fill Polygon, Odd/Even            | ✓                                 | ✓  |
| FP                                 | Fill Polygon, Non-Zero Winding    | ✓                                 | ✓  |
| FT                                 | Fill Type                         | ✓                                 | ✓  |
| FT                                 | Fill Type - 22                    | ✓                                 | ✓  |
| FT                                 | Fill Type - 9                     | ✓                                 | ✓  |
| IN                                 | Initialize                        | ✓                                 | ✓  |
| IP                                 | Input P1 and P2                   | ✓                                 | ✓  |
| IR                                 | Input Relative P1 and P2          | ✓                                 | ✓  |
| IW                                 | Input Window                      | ✓                                 | ✓  |
| LA                                 | Line Attributes                   | ✓                                 | ✓  |
| LB                                 | Label, Default Terminator = '03'x | ✓                                 | ✓  |
| LO                                 | Label Origin                      | ✓                                 | ✓  |
| LO                                 | Uses PCL Label Origin             | ✓                                 | ✓  |
| LT                                 | Line Type                         | ✓                                 | ✓  |
| MC                                 | Logical Operation                 | ✓                                 | ✓  |
| NP                                 | Number of Pens                    | ✓                                 | ✓  |

## Appendix A: PCL support

| ✓ = Supported<br>X = Not supported |                             | Printer model                     |  |
|------------------------------------|-----------------------------|-----------------------------------|--|
| Command                            | Function                    | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de, X466dte,<br>X466dwe |
| PA                                 | Plot Absolute               | ✓                                 | ✓  |
| PC                                 | Set Pen Color               | ✓                                 | ✓  |
| PD                                 | Pen Down                    | ✓                                 | ✓  |
| PE                                 | Polyline Encoded            | ✓                                 | ✓  |
| PM                                 | Polygon Mode                | ✓                                 | ✓  |
| PP                                 | Pixel Placement             | ✓                                 | ✓  |
| PR                                 | Plot Relative               | ✓                                 | ✓  |
| PU                                 | Pen Up                      | ✓                                 | ✓  |
| PW                                 | Pen Width                   | ✓                                 | ✓  |
| RA                                 | Fill Rectangle Absolute     | ✓                                 | ✓  |
| RF                                 | Define Raster Fill          | ✓                                 | ✓  |
| RO                                 | Rotate Coordinate System    | ✓                                 | ✓  |
| RR                                 | Fill Rectangle Relative     | ✓                                 | ✓  |
| RT                                 | Arc Relative Three Point    | ✓                                 | ✓  |
| SA                                 | Select Alternate Font       | ✓                                 | ✓  |
| SB                                 | Scalable/Bitmapped Fonts    | ✓                                 | ✓  |
| SC                                 | Scale                       | ✓                                 | ✓  |
| SD                                 | Define Standard Font        | ✓                                 | ✓  |
| SI                                 | Absolute Character Size     | ✓                                 | ✓  |
| SL                                 | Character Slant             | ✓                                 | ✓  |
| SM                                 | Symbol Mode                 | ✓                                 | ✓  |
| SP                                 | Select Pen                  | ✓                                 | ✓  |
| SR                                 | Relative Character Size     | ✓                                 | ✓  |
| SS                                 | Select Standard Font        | ✓                                 | ✓  |
| SV                                 | Screened Vectors            | ✓                                 | ✓  |
| SV                                 | Screened Vectors - 9, level | ✓                                 | ✓  |

## Appendix A: PCL support

| ✓ = Supported<br>X = Not supported |                   | Printer model                     |  |
|------------------------------------|-------------------|-----------------------------------|--|
| Command                            | Function          | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de, X466dte,<br>X466dwe |
| TD                                 | Transparent Data  | ✓                                 | ✓  |
| TM                                 | Threshold Matrix  | ✓                                 | ✓  |
| TR                                 | Transparency Mode | ✓                                 | ✓  |
| UL                                 | User Defined Line | ✓                                 | ✓  |
| WG                                 | Wedge Fill        | ✓                                 | ✓  |
| WU                                 | Pen Width Units   | ✓                                 | ✓  |

## Appendix A: PCL support

# Appendix B: PJI support

## Common variables for both printer languages

| Variable name     | Printer model                  |  |
|-------------------|--------------------------------|--|
|                   | X264dn, X363dn, X364dn, X364dw | X463de, X464de, X466de, X466dte, X466dwe |
| AUTOCONT          | √                              | √  |
| AUTOSELECT        | x                              | x  |
| BINDING           | √                              | √  |
| BITSPERPIXEL      | √                              | √  |
| CLEARABLEWARNINGS | √                              | √  |
| CONTEXTSWITCH     | x                              | x  |
| COPIES            | √                              | √  |
| CPLOCK            | √                              | √  |
| DENSITY           | √                              | √  |
| DISKLOCK          | x                              | x  |
| DUPLEX            | √                              | √  |
| ECONOMODE         | √                              | √  |
| FORMATTERNUMBER   | √                              | √  |
| FORMLINES         | √                              | √  |
| HELDJOBTIMEOUT    | x                              | √  |
| HOLD              | x                              | √  |
| HOLDKEY           | x                              | √  |
| HOLDTYPE          | x                              | √  |
| IMAGEADAPT        | x                              | x  |
| INTRAY1           | x                              | x  |
| INTRAY2           | √                              | √  |
| INTRAY3           | √                              | √  |
| INTRAY4           | √                              | √  |

| <b>√ = Supported</b><br><b>X = Not supported</b> | Printer model                  |  |
|--|--------------------------------|--|
|  | X264dn, X363dn, X364dn, X364dw | X463de, X464de, X466de, X466dte, X466dwe |
| INTRAY5  | √                              | √  |
| INTRAY1SIZE                                      | √                              | √  |
| INTRAY2SIZE                                      | √                              | √  |
| INTRAY3SIZE                                      | √                              | √  |
| INTRAY4SIZE                                      | √                              | √  |
| INTRAY5SIZE                                      | √                              | √  |
| IOBUFFER   | X                              | X  |
| IOSIZE   | X                              | X  |
| JOBATTR  | X                              | X  |
| JOBNAME  | √                              | √  |
| JOBOFFSET  | X                              | X  |
| LANG   | √                              | √  |
| LOWTONER   | √                              | √  |
| MANUALFEED                                       | √                              | √  |
| MEDIASOURCE                                      | X                              | X  |
| MEDIATYPE  | √                              | √  |
| MPTRAY   | √                              | √  |
| ORIENTATION                                      | √                              | √  |
| OUTBIN   | √                              | √  |
| PAGEPROTECT                                      | √                              | √  |
| PAPER  | √                              | √  |
| PARALLEL   | X                              | √  |
| PASSWORD   | √                              | √  |
| PERSONALITY                                      | √                              | √  |
| POWERSAVE  | √                              | √  |
| POWERSAVETIME                                    | √                              | √  |
| PRINTQUALITY                                     | X                              | X  |

## Appendix B: PjL support



| Variable name    | Printer model                  |  |
|------------------|--------------------------------|--|
|                  | X264dn, X363dn, X364dn, X364dw | X463de, X464de, X466de, X466dte, X466dwe |
| QTY              | ✓                              | ✓  |
| RENDERMODE       | x                              | x  |
| REPRINT          | ✓                              | ✓  |
| RESOLUTION       | ✓                              | ✓  |
| RESOURCESAVE     | ✓                              | ✓  |
| RESOURCESAVESIZE | x                              | x  |
| RET              | x                              | x  |
| TIMEOUT          | ✓                              | ✓  |
| USERNAME         | ✓                              | ✓  |
| WIDEA4           | ✓                              | ✓  |

## Printer-unique PJI variables for both printer languages

| Variable name     | Printer model                  |  |
|-------------------|--------------------------------|--|
|                   | X264dn, X363dn, X364dn, X364dw | X463de, X464de, X466de, X466dte, X466dwe |
| LACTIVEBINRESET   | x                              | x  |
| LADVANCEDSTATUS   | x                              | ✓  |
| LALARMCONTROL     | ✓                              | ✓  |
| LASSIGNFEEDER     | x                              | x  |
| LAUTOCRLF         | ✓                              | ✓  |
| LAUTOLFCR         | ✓                              | ✓  |
| LBAYERSCREENLIMIT | ✓                              | ✓  |
| LBLANKPAGES       | ✓                              | ✓  |
| LBONDLENGTH       | x                              | x  |
| LBONDLOADING      | ✓                              | ✓  |

| <b>✓ = Supported</b><br><b>X = Not supported</b> | Printer model                     |  |
|--|-----------------------------------|--|
|  | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de, X466dte,<br>X466dwe |
| Variable name                                    |                                   |  |
| LBONDOUTBIN                                      | X                                 | X  |
| LBONDTEXTURE                                     | ✓                                 | ✓  |
| LBONDWEIGHT                                      | ✓                                 | ✓  |
| LBWLOCK  | X                                 | X  |
| LCANCEL  | ✓                                 | ✓  |
| LCARDSTOCKLENGTH                                 | X                                 | X  |
| LCARDSTOCKLOADING                                | X                                 | X  |
| LCARDSTOCKOUTBIN                                 | X                                 | X  |
| LCARDSTOCKTEXTURE                                | ✓                                 | ✓  |
| LCARDSTOCKWEIGHT                                 | ✓                                 | ✓  |
| LCOLLATION                                       | ✓                                 | ✓  |
| LCOLORBALANCEBLACK                               | X                                 | X  |
| LCOLORBALANCECYAN                                | X                                 | X  |
| LCOLORBALANCEMAGENTA                             | X                                 | X  |
| LCOLORBALANCEYELLOW                              | X                                 | X  |
| LCOLORCORRECTION                                 | ✓                                 | ✓  |
| LCOLORSAVER                                      | X                                 | X  |
| LCOLORTRAPPING                                   | X                                 | X  |
| LCOLOREDLENGTH                                   | ✓                                 | ✓  |
| LCOLOREDLOADING                                  | ✓                                 | ✓  |
| LCOLOREDOUTBIN                                   | X                                 | X  |
| LCOLOREDTEXTURE                                  | ✓                                 | ✓  |
| LCOLOREDWEIGHT                                   | ✓                                 | ✓  |
| LCOLORMODEL                                      | ✓                                 | ✓  |
| LCUSTOMPAPERUNITS                                | ✓                                 | ✓  |
| LCUSTOMPAPERWIDTH                                | ✓                                 | ✓  |
| LCUSTOMPAPERHEIGHT                               | ✓                                 | ✓  |
| LCUSTOMPAPERFEED                                 | ✓                                 | ✓  |

## Appendix B: PjL support

| <b>✓ = Supported</b><br><b>X = Not supported</b> | Printer model                     |  |
|--|-----------------------------------|--|
|  | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de, X466dte,<br>X466dwe |
| Variable name                                    |                                   |  |
| LCUSTOMTYPE1LENGTH                               | ✓                                 | ✓  |
| LCUSTOMTYPE1LOADING                              | ✓                                 | ✓  |
| LCUSTOMTYPE1MEDIA                                | ✓                                 | ✓  |
| LCUSTOMTYPE1NAME                                 | ✓                                 | ✓  |
| LCUSTOMTYPE1OUTBIN                               | X                                 | X  |
| LCUSTOMTYPE1TEXTURE                              | ✓                                 | ✓  |
| LCUSTOMTYPE1WEIGHT                               | ✓                                 | ✓  |
| LCUSTOMTYPE2LENGTH                               | ✓                                 | ✓  |
| LCUSTOMTYPE2LOADING                              | ✓                                 | ✓  |
| LCUSTOMTYPE2MEDIA                                | ✓                                 | ✓  |
| LCUSTOMTYPE2NAME                                 | ✓                                 | ✓  |
| LCUSTOMTYPE2OUTBIN                               | X                                 | X  |
| LCUSTOMTYPE2TEXTURE                              | ✓                                 | ✓  |
| LCUSTOMTYPE2WEIGHT                               | ✓                                 | ✓  |
| LCUSTOMTYPE3LENGTH                               | ✓                                 | ✓  |
| LCUSTOMTYPE3LOADING                              | ✓                                 | ✓  |
| LCUSTOMTYPE3MEDIA                                | ✓                                 | ✓  |
| LCUSTOMTYPE3NAME                                 | ✓                                 | ✓  |
| LCUSTOMTYPE3OUTBIN                               | X                                 | X  |
| LCUSTOMTYPE3TEXTURE                              | ✓                                 | ✓  |
| LCUSTOMTYPE3WEIGHT                               | ✓                                 | ✓  |
| LCUSTOMTYPE4LENGTH                               | ✓                                 | ✓  |
| LCUSTOMTYPE4LOADING                              | ✓                                 | ✓  |
| LCUSTOMTYPE4MEDIA                                | ✓                                 | ✓  |
| LCUSTOMTYPE4NAME                                 | ✓                                 | ✓  |
| LCUSTOMTYPE4OUTBIN                               | X                                 | X  |

## Appendix B: PjL support

| <b>✓ = Supported</b><br><b>X = Not supported</b> | Printer model                     |  |
|--|-----------------------------------|--|
|  | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de, X466dte,<br>X466dwe |
| Variable name                                    |                                   |  |
| LCUSTOMTYPE4TEXTURE                              | ✓                                 | ✓  |
| LCUSTOMTYPE4WEIGHT                               | ✓                                 | ✓  |
| LCUSTOMTYPE5LENGTH                               | ✓                                 | ✓  |
| LCUSTOMTYPE5LOADING                              | ✓                                 | ✓  |
| LCUSTOMTYPE5MEDIA                                | ✓                                 | ✓  |
| LCUSTOMTYPE5NAME                                 | ✓                                 | ✓  |
| LCUSTOMTYPE5OUTBIN                               | X                                 | X  |
| LCUSTOMTYPE5TEXTURE                              | ✓                                 | ✓  |
| LCUSTOMTYPE5WEIGHT                               | ✓                                 | ✓  |
| LCUSTOMTYPE6LENGTH                               | ✓                                 | ✓  |
| LCUSTOMTYPE6LOADING                              | ✓                                 | ✓  |
| LCUSTOMTYPE6MEDIA                                | ✓                                 | ✓  |
| LCUSTOMTYPE6NAME                                 | ✓                                 | ✓  |
| LCUSTOMTYPE6OUTBIN                               | ✓                                 | ✓  |
| LCUSTOMTYPE6TEXTURE                              | ✓                                 | ✓  |
| LCUSTOMTYPE6WEIGHT                               | ✓                                 | ✓  |
| LDOWNLOADTARGET                                  | ✓                                 | ✓  |
| LDRYTIMEDELAY                                    | X                                 | X  |
| LDUPLEXLEFTMARGINOFFSET                          | ✓                                 | ✓  |
| LDUPLEXTOPMARGINOFFSET                           | ✓                                 | ✓  |
| LDUPLICATEHELDJOBS                               | X                                 | ✓  |
| LECOMODE   | ✓                                 | ✓  |
| LENVELOPEENHANCE                                 | X                                 | X  |
| LENVELOPELENGTH                                  | ✓                                 | ✓  |
| LENVELOPEOUTBIN                                  | X                                 | X  |
| LENVELOPETEXTURE                                 | ✓                                 | ✓  |

## Appendix B: PjL support

| <b>✓ = Supported</b><br><b>X = Not supported</b> | Printer model                     |  |
|--|-----------------------------------|--|
|  | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de, X466dte,<br>X466dwe |
| Variable name                                    |                                   |  |
| LENVELOPEWEIGHT                                  | ✓                                 | ✓  |
| LESCCHAR   | ✓                                 | ✓  |
| LFAXJOBWAITFORTONER                              | X                                 | ✓  |
| LFAXRESOLUTION                                   | ✓                                 | ✓  |
| LFAXREDIAL                                       | ✓                                 | ✓  |
| LFAXREDIALFREQUENCY                              | ✓                                 | ✓  |
| LFAXTRANSMISSIONLOG                              | ✓                                 | ✓  |
| LFEDERPAPERTYPE                                  | X                                 | X  |
| LGLOSSYLOADING                                   | X                                 | X  |
| LGLOSSYOUTBIN                                    | X                                 | X  |
| LGLOSSYOUTPUTBIN                                 | X                                 | X  |
| LGLOSSYTEXTURE                                   | X                                 | X  |
| LGLOSSYWEIGHT                                    | X                                 | X  |
| LHEAVYGLOSSYLOADING                              | X                                 | X  |
| LHEAVYGLOSSYOUTBIN                               | X                                 | X  |
| LHEAVYGLOSSYTEXTURE                              | X                                 | X  |
| LHEAVYGLOSSYWEIGHT                               | X                                 | X  |
| LHEAVYPAPERLOADING                               | ✓                                 | ✓  |
| LHEAVYPAPEROUTBIN                                | X                                 | X  |
| LHEAVYPAPERTEXTURE                               | ✓                                 | ✓  |
| LHEAVYPAPERWEIGHT                                | ✓                                 | ✓  |
| LHOLEPUNCHALARM                                  | X                                 | X  |
| LHOLEPUNCHMODE                                   | X                                 | X  |
| LHONORINIT                                       | X                                 | ✓  |
| LIMAGEBRIGHTNESS                                 | ✓                                 | ✓  |
| LIMAGECONTRAST                                   | ✓                                 | ✓  |
| LIMAGEENHANCE                                    | ✓                                 | ✓  |
| LIMAGEENHANCETYPE                                | ✓                                 | ✓  |

## Appendix B: PJL support

| <b>✓ = Supported</b><br><b>X = Not supported</b> | Printer model                     |  |
|--|-----------------------------------|--|
|  | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de, X466dte,<br>X466dwe |
| Variable name                                    |                                   |  |
| LIMAGEORIENTATION                                | ✓                                 | ✓  |
| LIMAGESATURATION                                 | X                                 | X  |
| LIMAGESMOOTHING                                  | X                                 | X  |
| LINFEDER   | ✓                                 | X  |
| LINFEDERSIZE                                     | X                                 | X  |
| LINKALERT  | X                                 | X  |
| LINMPFEEDERSIZE                                  | ✓                                 | ✓  |
| LJAMRECOVERY                                     | ✓                                 | ✓  |
| LLABELSLENGTH                                    | X                                 | X  |
| LLABELSLOADING                                   | X                                 | X  |
| LLABELSOUTBIN                                    | X                                 | X  |
| LLABELSTEXTURE                                   | ✓                                 | ✓  |
| LLABELSWEIGHT                                    | ✓                                 | ✓  |
| LLEFTMARGINOFFSET                                | ✓                                 | ✓  |
| LLETTERHEADLENGTH                                | X                                 | X  |
| LLETTERHEADLOADING                               | ✓                                 | ✓  |
| LLETTERHEADOUTBIN                                | X                                 | X  |
| LLETTERHEADTEXTURE                               | ✓                                 | ✓  |
| LLETTERHEADWEIGHT                                | ✓                                 | ✓  |
| LLIGHTPAPERLOADING                               | ✓                                 | ✓  |
| LLIGHTPAPEROUTBIN                                | X                                 | X  |
| LLIGHTPAPERTEXTURE                               | ✓                                 | ✓  |
| LLIGHTPAPERWEIGHT                                | ✓                                 | ✓  |
| LLINEDetail                                      | ✓                                 | ✓  |
| LMANUALCOLORRGBTEXT                              | X                                 | X  |
| LMANUALCOLORRGBGRAPHICS                          | X                                 | X  |
| LMANUALCOLORRGBIMAGE                             | X                                 | X  |
| LMANUALCOLORCMYKTEXT                             | X                                 | X  |

## Appendix B: PjL support

| <b>✓ = Supported</b><br><b>X = Not supported</b> | Printer model                     |  |
|--|-----------------------------------|--|
|  | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de, X466dte,<br>X466dwe |
| Variable name                                    |                                   |  |
| LMANUALCOLORCMYKGRAPHICS                         | X                                 | X  |
| LMANUALCOLORCMYKIMAGE                            | X                                 | X  |
| LMANUALENVELOPESIZE                              | ✓                                 | ✓  |
| LMANUALENVELOPETYPE                              | ✓                                 | ✓  |
| LMANUALPAPERSIZE                                 | ✓                                 | ✓  |
| LMANUALPAPERTYPE                                 | ✓                                 | ✓  |
| LMAXSTATUSMSG                                    | X                                 | X  |
| LMPFEEDERPAPERTYPE                               | ✓                                 | ✓  |
| LMULTIPAGEBORDER                                 | ✓                                 | ✓  |
| LMULTIPAGEORDER                                  | ✓                                 | ✓  |
| LMULTIPAGEPRINT                                  | ✓                                 | ✓  |
| LMULTIPAGEVIEW                                   | ✓                                 | ✓  |
| LNPAP  | ✓                                 | ✓  |
| LOPTIONALOUTBIN1NAME                             | X                                 | X  |
| LOPTIONALOUTBIN2NAME                             | X                                 | X  |
| LOPTIONALOUTBIN3NAME                             | X                                 | X  |
| LOPTIONALOUTBIN4NAME                             | X                                 | X  |
| LOPTIONALOUTBIN5NAME                             | X                                 | X  |
| LOPTIONALOUTBIN6NAME                             | X                                 | X  |
| LOPTIONALOUTBIN7NAME                             | X                                 | X  |
| LOPTIONALOUTBIN8NAME                             | X                                 | X  |
| LOPTIONALOUTBIN9NAME                             | X                                 | X  |
| LOPTIONALOUTBIN10NAME                            | X                                 | X  |
| LOUTBINCONFIG                                    | X                                 | X  |
| LOVERFLOWOUTBIN                                  | X                                 | X  |
| LOVERFLOWTIMER                                   | X                                 | X  |
| LPAGECOUNT                                       | ✓                                 | ✓  |
| LPAGEMODE  | ✓                                 | ✓  |

## Appendix B: PjL support

| Variable name      | Printer model                     |  |
|--------------------|-----------------------------------|--|
|                    | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de, X466dte,<br>X466dwe |
| LPAPERSOURCE       | ✓                                 | ✓  |
| LPICTUREGRADE      | X                                 | X  |
| LPLAINLENGTH       | X                                 | X  |
| LPLAINOUTBIN       | X                                 | X  |
| LPLAINTEXTURE      | ✓                                 | ✓  |
| LPLAINWEIGHT       | ✓                                 | ✓  |
| LPOWERSAVER        | ✓                                 | ✓  |
| LPPDS              | ✓                                 | ✓  |
| LPPDSFORMLINES     | ✓                                 | ✓  |
| LPPDSLINESPERINCH  | ✓                                 | ✓  |
| LPREPRINTEDLENGTH  | ✓                                 | ✓  |
| LPREPRINTEDLOADING | ✓                                 | ✓  |
| LPREPRINTEDOUTBIN  | X                                 | X  |
| LPREPRINTEDTEXTURE | ✓                                 | ✓  |
| LPREPRINTEDWEIGHT  | ✓                                 | ✓  |
| LPRINTBUFFER       | ✓                                 | ✓  |
| LPRINTHEADIDLETIME | X                                 | X  |
| LPRINTERUSAGE      | X                                 | X  |
| LPRINTMENUSBUTTON  | X                                 | X  |
| LPRINTQUALITY      | X                                 | X  |
| LPUNCH             | X                                 | X  |
| LQUIETMODE         | ✓                                 | ✓  |
| LREAROUTBINNAME    | X                                 | X  |
| LRECYCLEDLOADING   | ✓                                 | ✓  |
| LRECYCLEDOUTBIN    | X                                 | X  |
| LRECYCLEDMEDIA     | ✓                                 | ✓  |
| LRECYCLEDTEXTURE   | ✓                                 | ✓  |

## Appendix B: PjL support



| <b>✓ = Supported</b><br><b>X = Not supported</b> | Printer model                     |  |
|--|-----------------------------------|--|
|  | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de, X466dte,<br>X466dwe |
| Variable name                                    |                                   |  |
| LRECYCLEDWEIGHT                                  | ✓                                 | ✓  |
| LREPEATPRINTLIMIT                                | X                                 | X  |
| LRESET   | X                                 | ✓  |
| LRESOURCESAVE                                    | ✓                                 | ✓  |
| LRIGHTMARGINOFFSET                               | ✓                                 | ✓  |
| LROUGHENVELOPELOADING                            | X                                 | X  |
| LROUGHENVELOPEOUTBIN                             | X                                 | X  |
| LROUGHENVELOPETEXTURE                            | ✓                                 | ✓  |
| LROUGHENVELOPEWEIGHT                             | ✓                                 | ✓  |
| LROUGHHPAPERLOADING                              | X                                 | X  |
| LROUGHHPAPEROUTBIN                               | X                                 | X  |
| LROUGHHPAPERTEXTURE                              | ✓                                 | ✓  |
| LROUGHHPAPERWEIGHT                               | ✓                                 | ✓  |
| LSCREENING                                       | X                                 | X  |
| LSEPARATORSHEETS                                 | ✓                                 | ✓  |
| LSEPARATORSOURCE                                 | ✓                                 | ✓  |
| LSMALLFONTENHANCER                               | ✓                                 | ✓  |
| LSSGALVO   | X                                 | X  |
| LSTANDARDOUTBINNAME                              | ✓                                 | ✓  |
| LSTAPLE  | X                                 | X  |
| LSTAPLEEMPTYALARM                                | X                                 | X  |
| LSTAPLETESTBIN                                   | X                                 | X  |
| LSTAPLETESTSOURCE                                | X                                 | X  |
| LSTROKEWIDTH                                     | X                                 | X  |
| LSUBSTITUTESIZE                                  | X                                 | ✓  |
| LTOPBINROTATE                                    | X                                 | X  |
| LTOPMARGINOFFSET                                 | ✓                                 | ✓  |
| LTRANSPARENCYLENGTH                              | X                                 | X  |

## Appendix B: PjL support

| Variable name               | Printer model                     |  |
|-----------------------------|-----------------------------------|--|
|                             | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de, X466dte,<br>X466dwe |
| LTRANSPARENCYOUTBIN         | X                                 | X  |
| LTRANSPARENCYTEXTURE        | ✓                                 | ✓  |
| LTRANSPARENCYWEIGHT         | ✓                                 | ✓  |
| LTRAY1AUTOSIZE              | X                                 | ✓  |
| LTRAY2AUTOSIZE              | X                                 | ✓  |
| LTRAY3AUTOSIZE              | X                                 | ✓  |
| LTRAY1PAPERTYPE             | ✓                                 | ✓  |
| LTRAY2PAPERTYPE             | ✓                                 | ✓  |
| LTRAY3PAPERTYPE             | ✓                                 | ✓  |
| LTRAY4PAPERTYPE             | ✓                                 | ✓  |
| LTRAY5PAPERTYPE             | ✓                                 | ✓  |
| LTRAY1RENUMBER              | ✓                                 | ✓  |
| LTRAY1SENSEDTYPEPAPER       | X                                 | X  |
| LTRAY1SENSEDTYPETRANSARENCY | X                                 | X  |
| LTRAY2SENSEDTYPEPAPER       | X                                 | X  |
| LTRAY2SENSEDTYPETRANSARENCY | X                                 | X  |
| LTRAY3SENSEDTYPEPAPER       | X                                 | X  |
| LTRAY3SENSEDTYPETRANSARENCY | X                                 | X  |
| LTRAY4SENSEDTYPEPAPER       | X                                 | X  |
| LTRAY4SENSEDTYPETRANSARENCY | X                                 | X  |
| LTYPE1FONTS                 | ✓                                 | ✓  |
| LUSDEFAULTS                 | ✓                                 | ✓  |
| LVINYLLABELSLOADING         | X                                 | X  |
| LVINYLLABELSOUTBIN          | X                                 | X  |
| LVINYLLABELSTEXTURE         | X                                 | X  |
| LVINYLLABELSWEIGHT          | X                                 | X  |
| LWRITECOVERAGE              | ✓                                 | ✓  |

## Appendix B: PjL support

# Common variables for PCL emulation

| Variable name | Printer model                     |  |
|---------------|-----------------------------------|--|
|               | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de, X466dte,<br>X466dwe |
| FONTNUMBER    | ✓                                 | ✓  |
| FONTSOURCE    | ✓                                 | ✓  |
| PITCH         | ✓                                 | ✓  |
| PTSIZE        | ✓                                 | ✓  |
| SYMSET        | ✓                                 | ✓  |

# Printer-unique variables for PCL emulation

| Variable name         | Printer model                     |  |
|-----------------------|-----------------------------------|--|
|                       | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de, X466dte,<br>X466dwe |
| LA4WIDTH              | ✓                                 | ✓  |
| LASSIGNFEEDER         | X                                 | X  |
| LASSIGNMANUALENVELOPE | ✓                                 | ✓  |
| LASSIGNMANUALPAPER    | ✓                                 | ✓  |
| LASSIGNMPFEEDER       | ✓                                 | ✓  |
| LASSIGNTRAY1          | ✓                                 | ✓  |
| LASSIGNTRAY2          | ✓                                 | ✓  |
| LASSIGNTRAY3          | ✓                                 | ✓  |
| LASSIGNTRAY4          | ✓                                 | ✓  |
| LASSIGNTRAY5          | ✓                                 | ✓  |
| LBITMAPROUNDING       | ✓                                 | ✓  |
| LCOLOREXTENSIONS      | ✓                                 | ✓  |
| LFONTCOMPATIBILITY    | ✓                                 | ✓  |

| ✓ = Supported<br>X = Not supported | Printer model                     |  |
|------------------------------------|-----------------------------------|--|
| Variable name                      | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de, X466dte,<br>X466dwe |
| LFONTPRIORITY                      | ✓                                 | ✓  |

## Common variables for PostScript emulation

| ✓ = Supported<br>X = Not supported | Printer model                     |  |
|------------------------------------|-----------------------------------|--|
| Variable name                      | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de, X466dte,<br>X466dwe |
| ADOBEMBT                           | X                                 | X  |
| JAMRECOVERY                        | ✓                                 | ✓  |
| PRTPSERRS                          | ✓                                 | ✓  |

## Printer-unique variables for PostScript emulation

| ✓ = Supported<br>X = Not supported | Printer model                     |  |
|------------------------------------|-----------------------------------|--|
| Variable name                      | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de, X466dte,<br>X466dwe |
| LPICTUREGRADE                      | X                                 | X  |
| LPSFONTPRIORITY                    | ✓                                 | ✓  |

## Printer-unique LRESOURCE variables

| ✓ = Supported<br>X = Not supported | Printer model                     |  |
|------------------------------------|-----------------------------------|--|
| Variable name                      | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de, X466dte,<br>X466dwe |
| LDESCRIPTION                       | ✓                                 | ✓  |
| LRWLOCK                            | ✓                                 | ✓  |

| Variable name | Printer model                     |  |
|---------------|-----------------------------------|--|
|               | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de, X466dte,<br>X466dwe |
| LWLOCK        | ✓                                 | ✓  |

## Status Readback commands

| Variable name | Printer model                     |  |
|---------------|-----------------------------------|--|
|               | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de, X466dte,<br>X466dwe |
| Dinquire      | ✓                                 | ✓  |
| Echo          | ✓                                 | ✓  |
| Info          | ✓                                 | ✓  |
| Inquire       | ✓                                 | ✓  |
| Ustatus       | ✓                                 | ✓  |
| Ustatusoff    | ✓                                 | ✓  |

## USTATUS unsolicited status variables

| Variable name | Printer model                     |  |
|---------------|-----------------------------------|--|
|               | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de, X466dte,<br>X466dwe |
| DEVICE        | ✓                                 | ✓  |
| JOB           | ✓                                 | ✓  |
| PAGE          | ✓                                 | ✓  |
| TIMED         | ✓                                 | ✓  |

# PJL messages for auto-continuable conditions

| ✓ = Supported<br>X = Not supported                           |             |   | Printer model                     |  |
|--|-------------|---|-----------------------------------|--|
| Message  | Status code | Return string   | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de, X466dte,<br>X466dwe |
| Intervention Required -<br>PPDS Font Error                   | 30014       | 50 PPDS Font Error  | ✓                                 | ✓  |
| Intervention Required -<br>Insufficient Collation<br>Area    | 30016       | 37 Insufficient<br>Collation Area                                     | ✓                                 | ✓  |
| Intervention Required -<br>Insufficient Defragment<br>Memory | 30016       | 37 Insufficient<br>Defrag Memory                                      | ✓                                 | X  |
| Intervention Required -<br>Insufficient Memory               | 30016       | 37 Insufficient<br>Memory   | X                                 | ✓  |
| Intervention Required -<br>Insufficient Memory               | 30016       | 37 Insufficient<br>memory for Flash<br>Memory Defragment<br>operation | X                                 | X  |
| Intervention Required -<br>Insufficient Defragment<br>Memory | 30016       | 37 Insufficient<br>memory, some Held<br>Jobs were deleted             | X                                 | X  |
| Intervention Required -<br>Insufficient Defragment<br>Memory | 30016       | 37 Insufficient<br>memory, some Held<br>Jobs will not be<br>restored  | X                                 | X  |
| Intervention Required -<br>Insufficient Collation<br>Area    | 30016       | 37 Insufficient<br>memory to collate<br>job                           | X                                 | X  |
| Intervention Required -<br>Memory Full                       | 30016       | 38 Memory Full  | ✓                                 | ✓  |
| Intervention Required -<br>Configuration Change              | 30016       | 57 Configuration<br>Change  | X                                 | X  |
| Intervention Required -<br>Configuration Change              | 30016       | 57 Configuration<br>change, some held<br>jobs were not<br>restored    | X                                 | X  |
| Intervention Required -<br>Held Jobs May Not Be<br>Restored  | 30016       | Held Jobs May Not<br>Be Restored                                      | X                                 | ✓  |

| ✓ = Supported<br>X = Not supported                                |             |  | Printer model                     |  |
|---|-------------|--|-----------------------------------|--|
| Message   | Status code | Return string                            | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de, X466dte,<br>X466dwe |
| Intervention Required -<br>Held Jobs May Not Be<br>Restored       | 30016       | Some held jobs<br>were not restored      | X                                 | X  |
| Intervention Required -<br>Complex Page                           | 30017       | 39 Complex Page                          | ✓                                 | ✓  |
| Intervention Required -<br>Parallel Error                         | 30018       | 54 Parallel Error                        | X                                 | X  |
| Intervention Required -<br>Serial Option Error                    | 30018       | 54 Serial option<br><slot #> error       | X                                 | X  |
| Intervention Required -<br>Network Software Error                 | 30018       | 54 Standard<br>Network Software<br>Error | ✓                                 | ✓  |
| Intervention Required -<br>Standard Serial Error                  | 30018       | 54 Standard Serial<br>Error              | X                                 | X  |
| Intervention Required -<br>Network Software Error                 | 30018       | 54 Standard<br>network software<br>error | ✓                                 | ✓  |
| Intervention Required -<br>Network Software Error                 | 30018       | 54 Std Network<br>Software Error         | ✓                                 | ✓  |
| Intervention Required -<br>Standard Serial Fax<br>Connection Lost | 30018       | 54 Std Ser Fax<br>Connection Lost        | X                                 | X  |
| Intervention Required -<br>Parallel Port Disabled                 | 30018       | 56 Parallel Port<br>Disabled             | X                                 | X  |
| Intervention Required -<br>Parallel Port Error                    | 30018       | 56 Parallel Port<br>[x] Disabled         | X                                 | X  |
| Intervention Required -<br>Serial Option Disabled                 | 30018       | 56 Serial <slot #><br>Port Disabled      | X                                 | ✓  |
| Intervention Required -<br>Standard Serial Disabled               | 30018       | 56 Standard Serial<br>Disabled           | X                                 | X  |
| Intervention Required -<br>Standard USB Disabled                  | 30018       | 56 Standard USB<br>port disabled         | ✓                                 | ✓  |
| Intervention Required -<br>Std Parallel Port Disabled             | 30018       | 56 Std Parallel<br>Port Disabled         | X                                 | X  |

## Appendix B: PJI support

| ✓ = Supported<br>X = Not supported                         |             |   | Printer model                     |  |
|--|-------------|---|-----------------------------------|--|
| Message  | Status code | Return string                                       | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de, X466dte,<br>X466dwe |
| Intervention Required - Resource Save Off Deficient Memory | 30019       | 35 Res Save Off Deficient Memory                    | ✓                                 | ✓  |
| Intervention Required - Insufficient Fax Buffer            | 30026       | 55 Insufficient Fax Buffer                          | X                                 | X  |
| Intervention Required - Std Par ENA Connection Lost        | 30027       | 54 Std Par ENA Connection Lost                      | X                                 | X  |
| Intervention Required - Standard Parallel Port Disabled    | 30027       | 56 Standard Parallel Port Disabled                  | X                                 | X  |
| Intervention Required - Std Parallel Port Disabled         | 30027       | 56 Std Parallel Port Disabled                       | X                                 | X  |
| Intervention Required - Resolution Reduced                 | 30029       | 36 Resolution Reduced                               | X                                 | X  |
| Intervention Required - Print Jobs on Disk Request         | 30031       | Print Jobs on Disk? or Print Jobs on Disk. Go/Stop? | X                                 | X  |
| Intervention Required - Restore Held Jobs. Go/Stop?        | 30031       | Restore Held Jobs. Go/Stop?                         | X                                 | ✓  |
| Intervention Required - Short Paper                        | 30034       | 34 Short Paper                                      | ✓                                 | ✓  |
| Intervention Required - Flash Full                         | 30035       | 52 Flash Full                                       | X                                 | X  |
| Intervention Required - Disk Full                          | 30035       | 62 Disk Full  | X                                 | ✓  |
| Intervention Required - Defective Flash                    | 30036       | 51 Defective Flash                                  | ✓                                 | ✓  |
| Intervention Required - Unformatted Flash                  | 30036       | 53 Unformatted Flash                                | X                                 | X  |
| Intervention Required - Defective Disk                     | 30036       | 61 Defective Disk                                   | X                                 | ✓  |
| Intervention Required - Unformatted Disk                   | 30036       | 63 Unformatted Disk                                 | X                                 | ✓  |

## Appendix B: PJI support



| ✓ = Supported<br>X = Not supported                         |             |   | Printer model                     |  |
|--|-------------|---|-----------------------------------|--|
| Message  | Status code | Return string   | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de, X466dte,<br>X466dwe |
| Intervention Required - Scheduled Maintenance              | 30075       | 80 Scheduled Maintenance                                | X                                 | X  |
| Intervention Required - Scheduled Maintenance              | 30075       | 80 Scheduled maintenance ADF kit                        | X                                 | X  |
| Intervention Required - Insufficient Memory                | 30076       | 35 Insufficient memory to support Resource Save feature | ✓                                 | ✓  |
| Intervention Required - Resource Save Off Deficient Memory | 30076       | 35 Res Save Off Deficient Memory                        | ✓                                 | ✓  |
| Intervention Required - Insufficient Collation Area        | 30076       | 37 Insufficient Collation Area                          | X                                 | X  |
| Intervention Required - Service Required                   | 30095       | 36 Printer service required                             | X                                 | X  |
| Intervention Required - Empty Box M                        | 30107       | Empty Box M   | X                                 | X  |
| Intervention Required - Empty Hole Punch Box               | 30107       | Empty Hole Punch Box                                    | X                                 | X  |
| Intervention Required - Insert Box M                       | 30107       | Insert Box M  | X                                 | X  |
| Intervention Required - Insert Staple Cartridge            | 30107       | Insert staple cartridge                                 | X                                 | X  |
| Intervention Required - Insert Stapler                     | 30107       | Insert Stapler  | X                                 | X  |
| Intervention Required - Priming Failed                     | 30107       | Priming Failed, Retry. Go/Stop?                         | X                                 | X  |
| Intervention Required - Network <x> Software Error         | 30112       | 54 Network <x> Software Error                           | ✓                                 | ✓  |
| Intervention Required - Serial <x> Fax Connection Lost     | 30112       | 54 Ser <x> Fax Connection Lost                          | X                                 | X  |
| Intervention Required - Serial Option <x> Error            | 30112       | 54 Serial Option <x> Error                              | X                                 | X  |

## Appendix B: PJI support

| ✓ = Supported<br>X = Not supported                          |             |  | Printer model                     |  |
|---|-------------|--|-----------------------------------|--|
| Message   | Status code | Return string  | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de, X466dte,<br>X466dwe |
| Intervention Required - Serial Port <x> Disabled            | 30112       | 56 Serial Port <x> Disabled                            | ✓                                 | ✓  |
| Intervention Required - USB Port Disabled                   | 30112       | 56 USB Port <x> Disabled                               | X                                 | X  |
| Intervention Required - Parallel <x> ENA Connection Lost    | 30113       | 54 Par <x> ENA Connection Lost                         | X                                 | X  |
| Intervention Required - Parallel <x> Port Disabled          | 30113       | 56 Parallel Port <x> Disabled                          | X                                 | ✓  |
| Intervention Required - Disk Operation Failed Faxes on Disk | 32001       | Operation Failed Faxes on Disk                         | X                                 | X  |
| Intervention Required - Disk Operation Failed Jobs on Disk  | 32001       | Operation Failed Jobs on Disk                          | X                                 | X  |
| Intervention Required - Flash Full                          | 32002       | 52 Flash Full  | ✓                                 | ✓  |
| Intervention Required - Flash Full                          | 32002       | 52 Not enough free space in flash memory for resources | ✓                                 | ✓  |
| Intervention Required - Disk Full                           | 32002       | 62 Disk full   | X                                 | ✓  |
| Intervention required - Disk Corrupted                      | 32015       | Disk corrupted   | X                                 | X  |
| Intervention required - Disk Corrupted. Reformat?           | 32015       | Disk Corrupted. Reformat?                              | X                                 | ✓  |
| Intervention Required - Too Many Bins Attached              | 32030       | 58 Too many bins attached                              | X                                 | X  |
| Intervention Required - Too Many Flash Options Installed    | 32030       | 58 Too Many Flash Options                              | ✓                                 | ✓  |
| Intervention Required - Too Many Flash Options Installed    | 32030       | 58 Too many flash options installed                    | ✓                                 | ✓  |

## Appendix B: PjL support

| ✓ = Supported<br>X = Not supported                 |             |                               | Printer model                     |  |
|--|-------------|-------------------------------|-----------------------------------|--|
| Message  | Status code | Return string                 | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de, X466dte,<br>X466dwe |
| Intervention Required - Unformatted Flash          | 32052       | 53 Unformatted Flash          | ✓                                 | X  |
| Intervention Required - Unformatted Flash Detected | 32052       | 53 Unformatted flash detected | ✓                                 | X  |
| Intervention Required - Unformatted Disk           | 32052       | 63 Unformatted disk           | X                                 | ✓  |
| Intervention Required - Unsupported Disk Format    | 32052       | 64 Unsupported Disk Format    | X                                 | X  |
| Intervention Required - Defective Flash            | 32056       | 51 Defective Flash            | ✓                                 | ✓  |
| Intervention Required - Defective Flash            | 32056       | 51 Defective flash detected   | ✓                                 | ✓  |
| Intervention Required - Defective Disk             | 32056       | 61 Defective Disk             | X                                 | ✓  |
| Intervention Required - Defective Disk             | 32056       | 61 Remove defective disk      | X                                 | ✓  |
| Intervention Required - Scheduled Maintenance      | 35075       | 80 Scheduled Maintenance      | X                                 | X  |
| Intervention Required - Scheduled Maintenance      | 35075       | 81 Scheduled Maintenance      | X                                 | X  |
| Intervention Required - Belt Exhausted             | 40038       | 80 Belt Exhausted             | X                                 | X  |
| Intervention Required - Belt Life Warning          | 40038       | 80 Belt Life Warning          | X                                 | X  |
| Intervention Required - Fuser/Belt Exhausted       | 40038       | 80 Fuser/Belt Exhausted       | X                                 | X  |
| Intervention Required - Fuser/Belt Life Warning    | 40038       | 80 Fuser/Belt Life Warning    | X                                 | X  |
| Intervention Required - Fuser Exhausted            | 40038       | 80 Fuser Exhausted            | X                                 | X  |
| Intervention Required - Fuser Life Warning         | 40038       | 80 Fuser Life Warning         | X                                 | X  |

## Appendix B: PJI support

| ✓ = Supported<br>X = Not supported           |             |                         | Printer model                     |  |
|--|-------------|-------------------------|-----------------------------------|--|
| Message                                      | Status code | Return string           | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de, X466dte,<br>X466dwe |
| Intervention Required -<br>Fuser Maintenance | 40038       | 80 Fuser<br>Maintenance | X                                 | X  |
| Intervention Required -<br>ITU Maintenance   | 40038       | 83 ITU Maintenance      | X                                 | X  |

## PJL messages for attendance conditions

| ✓ = Supported<br>X = Not supported                              |             |  | Printer model                     |   |
|---|-------------|--|-----------------------------------|---|
| Message   | Status code | Return string  | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de,<br>X466dte,<br>X466dwe |
| Intervention Required -<br>Too Many Bins Attached               | 32030       | 58 Too many bins<br>attached   | X                                 | X   |
| Intervention Required -<br>Too Many Flash Options<br>Installed  | 32030       | 58 Too many flash<br>options installed                               | ✓                                 | ✓   |
| Intervention Required -<br>Remove Defective Disk                | 32056       | 61 Remove<br>defective disk  | X                                 | ✓   |
| Intervention Required -<br>Insert Hole Punch Box                | 40010       | Insert Hole Punch<br>Box   | X                                 | X   |
| Intervention Required -<br>Insert PC Cartridge                  | 40010       | Insert PC<br>Cartridge   | X                                 | X   |
| Intervention Required -<br>30 CMYK* Print Unit<br>Missing       | 40010       | 30 CMYK* Print<br>Unit Missing                                       | X                                 | X   |
| Intervention Required -<br>30 Coating Roll Missing              | 40010       | 30 Coating Roll<br>Missing   | X                                 | X   |
| Intervention Required -<br>Remove Originals from<br>Scanner ADF | 40019       | Remove originals<br>from the scanner<br>automatic document<br>feeder | ✓                                 | ✓   |

\* This message contains a subset of letters CMYK, where CMYK denotes Cyan, Magenta, Yellow, and Black cartridges, respectively.

| ✓ = Supported<br>X = Not supported                            |             |                                    | Printer model                     |   |
|---|-------------|------------------------------------|-----------------------------------|---|
| Message   | Status code | Return string                      | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de,<br>X466dte,<br>X466dwe |
| Intervention Required -<br>Install MICR cartridge             | 40020       | Install MICR<br>cartridge          | X                                 | X   |
| Intervention Required -<br>Cartridge Life Expired             | 40021       | Cartridge Life<br>Expired CMYK*    | X                                 | X   |
| Intervention Required -<br>Cartridge Life Warning             | 40021       | Cartridge Life<br>Warning CMYK*    | X                                 | X   |
| Intervention Required -<br>Change Cartridge Invalid<br>Refill | 40021       | Change Cartridge<br>Invalid Refill | X                                 | X   |
| Intervention Required -<br>Close Cover <c>                    | 40021       | Close Cover <c>                    | X                                 | X   |
| Intervention Required -<br>Printer Cover Open                 | 40021       | Close Cover                        | X                                 | X   |
| Intervention Required -<br>Close Toner Box Cover              | 40021       | Close Cover                        | X                                 | X   |
| Intervention Required -<br>Close Deflector G                  | 40021       | Close Deflector G                  | X                                 | X   |
| Intervention Required -<br>Close Door <d>                     | 40021       | Close Door <d>                     | X                                 | X   |
| Intervention Required -<br>Close Door Insert<br>Cartridge     | 40021       | Close door or<br>insert cartridge  | X                                 | X   |
| Intervention Required -<br>Close Finisher Door                | 40021       | Close Finisher<br>Door             | X                                 | X   |
| Intervention Required -<br>Close Finisher Side Door           | 40021       | Close Finisher<br>Side Door        | X                                 | X   |
| Intervention Required -<br>Close Finisher Top Cover           | 40021       | Close Finisher Top<br>Cover        | X                                 | X   |
| Intervention Required -<br>Close Front Door                   | 40021       | Close Front Door                   | ✓                                 | ✓   |
| Intervention Required -<br>Close Side Door                    | 40021       | Close Side Door                    | X                                 | X   |

\* This message contains a subset of letters CMYK, where CMYK denotes Cyan, Magenta, Yellow, and Black cartridges, respectively.

## Appendix B: PJI support

| ✓ = Supported<br>X = Not supported                     |             |  | Printer model                     |   |
|--|-------------|--|-----------------------------------|---|
| Message  | Status code | Return string  | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de,<br>X466dte,<br>X466dwe |
| Intervention Required -<br>Close Surface               | 40021       | Close surface H  | X                                 | X   |
| Intervention Required -<br>Close Cover                 | 40021       | Close top access<br>cover  | X                                 | ✓   |
| Intervention Required -<br>Close Cover and Door        | 40021       | Close top access<br>cover and front<br>door                            | ✓                                 | X   |
| Intervention Required -<br>Close Door                  | 40021       | Close <tray> door  | X                                 | X   |
| Intervention Required -<br>Close Tray <x> Top<br>Cover | 40021       | Close Tray <x> Top<br>Cover  | X                                 | X   |
| Intervention Required -<br>Printer Upper Door Open     | 40021       | Cover Open, Close<br>Top Covers, Close<br>Door, or Insert<br>Cartridge | X                                 | X   |
| Intervention Required -<br>Insert Print Cartridge      | 40021       | Insert Print<br>Cartridge  | X                                 | X   |
| Intervention Required -<br>Open Cover                  | 40021       | Open Cover   | X                                 | X   |
| Intervention Required -<br>Open Rear Door              | 40021       | Open Rear Door   | X                                 | X   |
| Intervention Required -<br>Invalid Refill              | 40021       | 30 Invalid Refill<br>Change Cartridge                                  | ✓                                 | ✓   |
| Intervention Required -<br>Defective Ink Cartridge     | 40021       | 31 Defective<br>Cartridge CMYK*  | X                                 | X   |
| Intervention Required -<br>Defective Print Cartridge   | 40021       | 31 Defective Print<br>Cartridge  | X                                 | X   |
| Intervention Required -<br>Missing Cartridge           | 40021       | 31 Missing<br>Cartridge CMYK*  | X                                 | X   |
| Intervention Required -<br>Missing Printhead           | 40021       | 31 Missing<br>Printhead  | X                                 | X   |

\* This message contains a subset of letters CMYK, where CMYK denotes Cyan, Magenta, Yellow, and Black cartridges, respectively.

## Appendix B: PJI support

| ✓ = Supported<br>X = Not supported                  |             |   | Printer model                     |   |
|---|-------------|---|-----------------------------------|---|
| Message   | Status code | Return string                                     | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de,<br>X466dte,<br>X466dwe |
| Intervention Required - Defective Print Cartridge   | 40021       | 31 Replace defective cartridge                    | X                                 | X   |
| Intervention Required - Invalid Refill              | 40021       | 31.yy Invalid refill, change cartridge            | X                                 | X   |
| Intervention Required - Defective Print Cartridge   | 40021       | 31.yy Replace defective cartridge                 | X                                 | X   |
| Intervention Required - Defective Print Cartridge   | 40021       | 31.yy Replace defective print cartridge           | X                                 | X   |
| Intervention Required - Unsupported Cartridge       | 40021       | 32 Unsupported Cartridge                          | X                                 | X   |
| Intervention Required - Unsupported CMYK* Cartridge | 40021       | 32 Unsupported CMYK* Cartridge                    | X                                 | X   |
| Intervention Required - Unsupported Print Cartridge | 40021       | 32 Unsupported Print Cartridge                    | X                                 | X   |
| Intervention Required - Unsupported Printhead       | 40021       | 32 Unsupported Printhead                          | X                                 | X   |
| Intervention Required - Unsupported Cartridge       | 40021       | 32.yy Cartridge part number unsupported by device | X                                 | X   |
| Intervention Required - Tray Size Sense Error       | 40021       | 40 Tray <x> Size Sense Error                      | X                                 | X   |
| Intervention Required - Open Bin Exit Tray          | 40021       | 41 Open Bin 1 Exit Tray                           | X                                 | X   |
| Intervention Required - Cartridge Region Mismatch   | 40021       | 42.xy Cartridge region mismatch                   | X                                 | X   |
| Intervention Required - Paper Jam                   | 40022       | 2xx Paper Jam                                     | ✓                                 | ✓   |

\* This message contains a subset of letters CMYK, where CMYK denotes Cyan, Magenta, Yellow, and Black cartridges, respectively.

## Appendix B: PJI support

| ✓ = Supported<br>X = Not supported                       |             |                                  | Printer model                     |   |
|--|-------------|----------------------------------|-----------------------------------|---|
| Message  | Status code | Return string                    | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de,<br>X466dte,<br>X466dwe |
| Intervention Required - Waste Toner Box Missing          | 40025       | 82.yy Waste toner box missing    | X                                 | X   |
| Intervention Required - Check Tray Connection            | 40027       | Check tray <source #> connection | X                                 | X   |
| Intervention Required - Install Tray <x> or Cancel Job   | 40027       | Install Tray <x>                 | X                                 | X   |
| Intervention Required - Install Tray <x> or Cancel Job   | 40027       | Install Tray <x> or Cancel Job   | X                                 | X   |
| Intervention Required - Install Envelope Feeder          | 40028       | Install envelope feeder          | X                                 | X   |
| Intervention Required - Install Env Feeder or Cancel Job | 40028       | Install Env Feed or Cancel Job   | X                                 | X   |
| Intervention Required - Reattach Envelope Feeder         | 40028       | Reattach Envelope Feeder         | X                                 | X   |
| Intervention Required - Reattach MP Feeder               | 40028       | Reattach MP Feeder               | X                                 | X   |
| Intervention Required - Check Finisher Installation      | 40029       | Check Finisher Installation      | X                                 | X   |
| Intervention Required - Check Mailbox Installation       | 40029       | Check Mailbox Installation       | X                                 | X   |
| Intervention Required - Install Bin <x> or Cancel Job    | 40029       | Install Bin <x> or Cancel Job    | X                                 | X   |
| Intervention Required - Reattach Bin                     | 40029       | Reattach bin <x>                 | X                                 | X   |
| Intervention Required - Reattach Bins                    | 40029       | Reattach Bins <bin #x-bin #y>    | X                                 | X   |

\* This message contains a subset of letters CMYK, where CMYK denotes Cyan, Magenta, Yellow, and Black cartridges, respectively.

## Appendix B: PJI support



| ✓ = Supported<br>X = Not supported                          |             |                             | Printer model                     |   |
|---|-------------|-----------------------------|-----------------------------------|---|
| Message   | Status code | Return string               | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de,<br>X466dte,<br>X466dwe |
| Intervention Required - Reattach Output Bin                 | 40029       | Reattach Output Bin <bin #> | X                                 | X   |
| Intervention Required - Tray Config Error                   | 40030       | 33 Tray <x> Config Error    | X                                 | X   |
| Intervention Required - Input Config Error                  | 40030       | 58 Input config error       | X                                 | X   |
| Intervention Required - Too Many Bins Attached              | 40030       | 58 Too Many Bins Attached   | X                                 | X   |
| Intervention Required - Too Many Disks Installed            | 40030       | 58 Too many disks installed | X                                 | X   |
| Intervention Required - Too Many Trays Attached             | 40030       | 58 Too many trays attached  | ✓                                 | ✓   |
| Intervention Required - Too Many Disks Installed            | 40036       | 58 Too Many Disks Installed | X                                 | X   |
| Intervention Required - PerfectFinish Missing               | 40037       | 31 PerfectFinish Missing    | X                                 | X   |
| Intervention Required - PerfectFinish Empty                 | 40037       | 87 PerfectFinish Empty      | X                                 | X   |
| Intervention Required - Replace Oil Coating Roll            | 40038       | Replace Oil Coating Roll    | X                                 | X   |
| Intervention Required - Replace PC Kit                      | 40038       | Replace PC Kit              | ✓                                 | ✓   |
| Intervention Required - Replace PC Kit To Continue          | 40038       | Replace PC Kit To Continue  | X                                 | X   |
| Intervention Required - Replace Toner Cartridge             | 40038       | Replace Toner Cartridge     | X                                 | X   |
| Intervention Required - Replace Toner Cartridge To Continue | 40038       | Replace Toner To Continue   | X                                 | X   |
| Intervention Required - 84 All Photo Devs Exhausted         | 40038       | 84 All Photo Devs Exhausted | X                                 | X   |

\* This message contains a subset of letters CMYK, where CMYK denotes Cyan, Magenta, Yellow, and Black cartridges, respectively.

## Appendix B: PJJ support

| ✓ = Supported<br>X = Not supported                            |             |                                    | Printer model                     |   |
|---|-------------|------------------------------------|-----------------------------------|---|
| Message   | Status code | Return string                      | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de,<br>X466dte,<br>X466dwe |
| Intervention Required -<br>84 Black Photo Dev<br>Exhausted    | 40038       | 84 Black Photo Dev<br>Exhausted    | X                                 | X   |
| Intervention Required -<br>84 Black Photo Dev Life<br>Warning | 40038       | 84 Black Photo Dev<br>Life Warning | X                                 | X   |
| Intervention Required -<br>84 Color Photo Dev Life<br>Warning | 40038       | 84 Color Photo Dev<br>Life Warning | X                                 | X   |
| Intervention Required -<br>Cartridge Low                      | 40038       | 88 Cartridge Low                   | ✓                                 | ✓   |
| Intervention Required -<br>Toner Low                          | 40038       | 88 Cartridge low                   | X                                 | X   |
| Intervention Required -<br>Cartridge Low                      | 40038       | 88 Cartridge<br>Low <CMYK>         | X                                 | X   |
| Intervention Required -<br>Toner Low                          | 40038       | 88 Toner is low                    | X                                 | X   |
| Intervention Required -<br>Toner Low                          | 40038       | 88 Toner Low                       | X                                 | X   |

\* This message contains a subset of letters CMYK, where CMYK denotes Cyan, Magenta, Yellow, and Black cartridges, respectively.

| ✓ = Supported<br>X = Not supported  |             |  | Printer model                     |   |
|---|-------------|--|-----------------------------------|---|
| Message   | Status code | Return string  | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de,<br>X466dte,<br>X466dwe |
| Intervention Required -<br>Toner Low  | 40038       | 88 Yellow Toner<br>Low   | X                                 | X   |
|   |             | 88 Magenta Toner<br>Low  |                                   |   |
|   |             | 88 Cyan Toner Low<br>88 Black Toner Low  |                                   |   |
|   |             | 88 Color Print<br>Cartridge Low<br>88 Black Print<br>Cartridge Low<br>88 Photo Print<br>Cartridge Low      | X                                 | X   |
|   |             | 88 Yellow Toner<br>Empty<br>88 Magenta Toner<br>Empty<br>88 Cyan Toner<br>Empty<br>88 Black Toner<br>Empty | X                                 | X   |
| Intervention Required -<br>Cartridge Nearly Low   | 40038       | 88.yy Cartridge<br>nearly low  | X                                 | X   |
| Intervention Required -<br>Cartridge Empty  | 40039       | 89 Cartridge<br>Empty <CMYK>   | X                                 | X   |
| Intervention Required -<br>Load Staples   | 40040       | Load Staples   | X                                 | X   |
| Intervention Required -<br>Priming Failed. Retry?   | 40041       | Priming Failed.<br>Retry?  | X                                 | X   |
| Intervention Required -<br>OPMSG  | 40048       | OPMSG message  | X                                 | X   |
| Intervention Required -<br>STMSG  | 40049       | STMSG message  | X                                 | X   |
| Intervention Required -<br>Replace Fuser  | 40050       | Replace Fuser  | X                                 | X   |
| * This message contains a subset of letters CMYK, where CMYK denotes Cyan, Magenta, Yellow, and Black cartridges, respectively. |             |  |                                   |   |

## Appendix B: PJI support

| ✓ = Supported<br>X = Not supported                         |             |                                    | Printer model                     |   |
|--|-------------|------------------------------------|-----------------------------------|---|
| Message  | Status code | Return string                      | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de,<br>X466dte,<br>X466dwe |
| Intervention Required -<br>Replace Transfer Kit            | 40050       | Replace Transfer<br>Kit            | X                                 | X   |
| Intervention Required -<br>Incompatible Bin <x>            | 40087       | 59 Incompatible<br>Bin <x>         | X                                 | X   |
| Intervention Required -<br>Incompatible Bin <x>            | 40087       | 59 Incompatible<br>output bin <x>  | X                                 | X   |
| Intervention Required -<br>Incompatible Duplex             | 40088       | 59 Incompatible<br>Duplex          | X                                 | X   |
| Intervention Required -<br>Incompatible Duplex             | 40088       | 59 Incompatible<br>duplex          | X                                 | X   |
| Intervention Required -<br>Incompatible Tray <x>           | 40089       | 59 Incompatible<br>Tray <x>        | X                                 | ✓   |
| Intervention Required -<br>Incompatible Tray <x>           | 40089       | 59 Incompatible<br>tray <x>        | X                                 | X   |
| Intervention Required -<br>Incompatible Envelope<br>Feeder | 40090       | 59 Incompatible<br>Envelope Feeder | X                                 | X   |
| Intervention Required -<br>Incompatible Envelope<br>Feeder | 40090       | 59 Incompatible<br>envelope feeder | X                                 | X   |
| Intervention Required -<br>Check Duplex<br>Connection      | 40095       | Check Duplex<br>Connection         | X                                 | X   |
| Intervention Required -<br>Check Duplex<br>Connection      | 40095       | Check duplex<br>connection         | X                                 | X   |
| Intervention Required -<br>Install Duplex or Cancel<br>Job | 40095       | Install Duplex or<br>Cancel Job    | X                                 | X   |
| Intervention Required -<br>Install Duplex or Cancel<br>Job | 40095       | Install duplex                     | X                                 | X   |

\* This message contains a subset of letters CMYK, where CMYK denotes Cyan, Magenta, Yellow, and Black cartridges, respectively.

## Appendix B: PJI support

| ✓ = Supported<br>X = Not supported                  |             |                                      | Printer model                     |   |
|---|-------------|--------------------------------------|-----------------------------------|---|
| Message   | Status code | Return string                        | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de,<br>X466dte,<br>X466dwe |
| Intervention Required - Duplex Cover Open           | 40096       | Close Duplex Door                    | X                                 | X   |
| Intervention Required - Insert Duplex Option        | 40096       | Insert Duplex Option                 | X                                 | X   |
| Intervention Required - Load Staples                | 40101       | Load Staples                         | X                                 | X   |
| Intervention Required - Insert Hole Punch Box       | 40107       | Insert the hole punch box            | X                                 | X   |
| Intervention Required - Replace Color PC Units      | 40129       | 84 Replace color PC Units            | X                                 | X   |
| Intervention Required - Replace Photoconductor      | 40129       | 84.yy Replace <color> photoconductor | X                                 | X   |
| Intervention Required - Replace Waste Toner Box     | 40141       | 82.yy Replace waste toner box        | X                                 | X   |
| Intervention Required - Waste Toner Box Nearly Full | 40141       | 82.yy Waste toner box nearly full    | X                                 | X   |
| Intervention Required - Transfer Module Missing     | 40143       | 83.yy Transfer module missing        | X                                 | ✓   |
| Intervention Required - Cartridge Low               | 40200       | 88.yy black cartridge low            | ✓                                 | ✓   |
| Intervention Required - Cartridge Nearly Low        | 40200       | 88.1x black cartridge nearly low     | X                                 | X   |
| Intervention Required - Replace Cartridge           | 40200       | 88.2x Replace black cartridge        | X                                 | X   |
| Intervention Required - Cartridge Low               | 40201       | 88.yy cyan cartridge low             | X                                 | X   |
| Intervention Required - Cartridge Nearly Low        | 40201       | 88.1x cyan cartridge nearly low      | X                                 | X   |

\* This message contains a subset of letters CMYK, where CMYK denotes Cyan, Magenta, Yellow, and Black cartridges, respectively.

## Appendix B: PJI support

| ✓ = Supported<br>X = Not supported                        |             |   | Printer model                     |   |
|---|-------------|---|-----------------------------------|---|
| Message   | Status code | Return string                                 | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de,<br>X466dte,<br>X466dwe |
| Intervention Required -<br>Replace Cartridge              | 40201       | 88.2x Replace cyan<br>cartridge               | X                                 | X   |
| Intervention Required -<br>Cartridge Low                  | 40202       | 88.yy magenta<br>cartridge low                | X                                 | X   |
| Intervention Required -<br>Cartridge Nearly Low           | 40202       | 88.1x magenta<br>cartridge nearly<br>low      | X                                 | X   |
| Intervention Required -<br>Replace Cartridge              | 40202       | 88.2x Replace<br>magenta cartridge            | X                                 | X   |
| Intervention Required -<br>Cartridge Low                  | 40203       | 88.yy yellow<br>cartridge low                 | X                                 | X   |
| Intervention Required -<br>Cartridge Nearly Low           | 40203       | 88.1x yellow<br>cartridge nearly<br>low       | X                                 | X   |
| Intervention Required -<br>Replace Cartridge              | 40203       | 88.2x Replace<br>yellow cartridge             | X                                 | X   |
| Black PC Unit Life<br>Warning                             | 40204       | 84 Black pc unit<br>life warning              | X                                 | X   |
| Intervention Required -<br>Unsupported PC Unit            | 40204       | 84 unsupported<br>[color] pc unit             | X                                 | X   |
| Intervention Required -<br>Color PC Units Life<br>Warning | 40204       | 84.yy Color PC<br>Unit Life warning           | X                                 | X   |
| Intervention Required -<br>PC Kit Life Warning            | 40204       | 84 PC kit life<br>warning                     | ✓                                 | ✓   |
| Intervention Required -<br>Photoconductor Low             | 40204       | 84.yy <color><br>photoconductor low           | X                                 | X   |
| Intervention Required -<br>Photoconductor Low             | 40204       | 84 Photoconductor<br>low                      | X                                 | X   |
| Intervention Required -<br>Photoconductor Nearly<br>Low   | 40204       | 84.yy [color]<br>photoconductor<br>nearly low | X                                 | X   |

\* This message contains a subset of letters CMYK, where CMYK denotes Cyan, Magenta, Yellow, and Black cartridges, respectively.

## Appendix B: PJI support

| ✓ = Supported<br>X = Not supported                              |             |  | Printer model                     |   |
|---|-------------|--|-----------------------------------|---|
| Message   | Status code | Return string  | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de,<br>X466dte,<br>X466dwe |
| Intervention Required -<br>Transfer Module Life<br>Warning      | 40215       | 83.yy Transfer<br>module life<br>warning                         | X                                 | X   |
| Intervention Required -<br>Transfer Module Near<br>Life Warning | 40215       | 83.yy Transfer<br>module near life<br>warning                    | X                                 | X   |
| Intervention Required -<br>Fuser Life Warning                   | 40216       | 87 Fuser Life<br>Warning   | X                                 | X   |
| Intervention Required -<br>Fuser Life Warning                   | 40216       | 80.yy Fuser life<br>warning                                      | X                                 | X   |
| Intervention Required -<br>Fuser Near Life Warning              | 40216       | 80.yy Fuser near<br>life warning                                 | X                                 | X   |
| Intervention Required -<br>Replace Toner                        | 40300       | 88 Replace black<br>toner  | X                                 | X   |
| Intervention Required -<br>Replace Toner                        | 40301       | 88 Replace cyan<br>toner   | X                                 | X   |
| Intervention Required -<br>Replace Toner                        | 40302       | 88 Replace magenta<br>toner                                      | X                                 | X   |
| Intervention Required -<br>Replace Toner                        | 40303       | 88 Replace yellow<br>toner                                       | X                                 | X   |
| Intervention Required -<br>Replace PC Kit                       | 40304       | 84 Replace PC Kit  | ✓                                 | ✓   |
| Intervention Required -<br>Replace Photoconductor               | 40304       | 84 Replace<br>photoconductor                                     | X                                 | X   |
| Intervention Required -<br>84 Replace Black PC Unit             | 40305       | 84 Replace black<br>PC Unit                                      | X                                 | X   |
| Intervention Required -<br>Cartridge Part Number<br>Unsupported | 40309       | 32.yy black<br>cartridge part<br>number unsupported<br>by device | X                                 | X   |
| Intervention Required -<br>Replace unsupported<br>cartridge     | 40309       | 32.yy Replace<br>unsupported black<br>cartridge                  | X                                 | X   |

\* This message contains a subset of letters CMYK, where CMYK denotes Cyan, Magenta, Yellow, and Black cartridges, respectively.

## Appendix B: PJI support

| ✓ = Supported<br>X = Not supported                        |             |   | Printer model                     |   |
|---|-------------|---|-----------------------------------|---|
| Message   | Status code | Return string   | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de,<br>X466dte,<br>X466dwe |
| Intervention Required - Invalid Refill, Change Cartridge  | 40309       | 40 black invalid refill, change cartridge                 | X                                 | X   |
| Intervention Required - Cartridge Part Number Unsupported | 40310       | 32.yy cyan cartridge part number unsupported by device    | X                                 | X   |
| Intervention Required - Replace unsupported cartridge     | 40310       | 32.yy Replace unsupported cyan cartridge                  | X                                 | X   |
| Intervention Required - Invalid Refill, Change Cartridge  | 40310       | 40 cyan invalid refill, change cartridge                  | X                                 | X   |
| Intervention Required - Cartridge Part Number Unsupported | 40311       | 32.yy magenta cartridge part number unsupported by device | X                                 | X   |
| Intervention Required - Replace unsupported cartridge     | 40311       | 32.yy Replace unsupported magenta cartridge               | X                                 | X   |
| Intervention Required - Invalid Refill, Change Cartridge  | 40311       | 40 magenta invalid refill, change cartridge               | X                                 | X   |
| Intervention Required - Cartridge Part Number Unsupported | 40312       | 32.yy yellow cartridge part number unsupported by device  | X                                 | X   |
| Intervention Required - Replace unsupported cartridge     | 40312       | 32.yy Replace unsupported yellow cartridge                | X                                 | X   |
| Intervention Required - Invalid Refill, Change Cartridge  | 40312       | 40 yellow invalid refill, change cartridge                | X                                 | X   |

\* This message contains a subset of letters CMYK, where CMYK denotes Cyan, Magenta, Yellow, and Black cartridges, respectively.

## Appendix B: PJI support



| ✓ = Supported<br>X = Not supported                           |             |  | Printer model                     |   |
|--|-------------|--|-----------------------------------|---|
| Message  | Status code | Return string  | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de,<br>X466dte,<br>X466dwe |
| Intervention Required -<br>Scheduled Maintenance             | 40315       | 80 Scheduled<br>maintenance [x]<br><b>Note:</b> [x] indicates 600k<br>kit. | X                                 | X   |
| Intervention Required -<br>Replace Transfer Module           | 40315       | 83.yy Replace<br>transfer module   | X                                 | X   |
| Intervention Required -<br>Replace Fuser                     | 40316       | 80.yy Replace<br>fuser   | X                                 | X   |
| Intervention Required -<br>Replace Fuser                     | 40316       | 87.yy Replace<br>fuser   | X                                 | X   |
| Intervention Required -<br>Scheduled Maintenance             | 40316       | 80 Scheduled<br>maintenance [x]<br><b>Note:</b> [x] indicates 100k<br>kit. | X                                 | X   |
| Intervention Required -<br>Replace Cartridge                 | 40400       | 31.yy Replace<br>defective or<br>missing cartridge                         | ✓                                 | ✓   |
| Intervention Required -<br>Insert Photoconductor             | 40404       | 84 Insert<br>photoconductor  | X                                 | X   |
| Intervention Required -                                      | 40404       | 84 Photoconductor<br>abnormal  | X                                 | X   |
| Intervention Required -<br><Color> PC Unit Missing           | 40405       | 84.41 Black PC<br>Unit missing   | X                                 | X   |
| Intervention Required -<br><Color><br>Photoconductor Missing | 40405       | 84.41 Black<br>photoconductor<br>missing                                   | X                                 | X   |
| Intervention Required -<br><Color> PC Unit Missing           | 40406       | 84.41 Cyan PC Unit<br>missing  | X                                 | X   |
| Intervention Required -<br><Color><br>Photoconductor Missing | 40406       | 84.41 Cyan<br>photoconductor<br>missing                                    | X                                 | X   |
| Intervention Required -<br><Color> PC Unit Missing           | 40407       | 84.41 Magenta PC<br>Unit missing   | X                                 | X   |

\* This message contains a subset of letters CMYK, where CMYK denotes Cyan, Magenta, Yellow, and Black cartridges, respectively.

## Appendix B: PJI support

| ✓ = Supported<br>X = Not supported                           |             |  | Printer model                     |   |
|--|-------------|--|-----------------------------------|---|
| Message  | Status code | Return string                                      | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de,<br>X466dte,<br>X466dwe |
| Intervention Required -<br><Color><br>Photoconductor Missing | 40407       | 84.41 Magenta<br>photoconductor<br>missing         | X                                 | X   |
| Intervention Required -<br><Color> PC Unit Missing           | 40408       | 84.41 Yellow PC<br>Unit missing                    | X                                 | X   |
| Intervention Required -<br><Color><br>Photoconductor Missing | 40408       | 84.41 Yellow<br>photoconductor<br>missing          | X                                 | X   |
| Intervention Required -<br>Toner Cartridge Missing           | 40409       | 30.yy Black toner<br>cartridge missing             | X                                 | X   |
| Intervention Required -<br>Defective Cartridge               | 40409       | 31.yy Defective<br>black cartridge                 | X                                 | X   |
| Intervention Required -<br>Missing or Defective<br>Cartridge | 40409       | 31.41 Missing or<br>defective black<br>cartridge   | X                                 | X   |
| Intervention Required -<br>Toner Cartridge Missing           | 40410       | 30.yy Cyan toner<br>cartridge missing              | X                                 | X   |
| Intervention Required -<br>Defective Cartridge               | 40410       | 31.yy Defective<br>cyan cartridge                  | X                                 | X   |
| Intervention Required -<br>Missing or Defective<br>Cartridge | 40410       | 31.41 Missing or<br>defective cyan<br>cartridge    | X                                 | X   |
| Intervention Required -<br>Toner Cartridge Missing           | 40411       | 30.yy Magenta<br>toner cartridge<br>missing        | X                                 | X   |
| Intervention Required -<br>Defective Cartridge               | 40411       | 31.yy Defective<br>magenta cartridge               | X                                 | X   |
| Intervention Required -<br>Missing or Defective<br>Cartridge | 40411       | 31.41 Missing or<br>defective magenta<br>cartridge | X                                 | X   |
| Intervention Required -<br>Toner Cartridge Missing           | 40412       | 30.yy Yellow toner<br>cartridge missing            | X                                 | X   |
| Intervention Required -<br>Defective Cartridge               | 40412       | 31.yy Defective<br>yellow cartridge                | X                                 | X   |

\* This message contains a subset of letters CMYK, where CMYK denotes Cyan, Magenta, Yellow, and Black cartridges, respectively.

## Appendix B: PJI support

| ✓ = Supported<br>X = Not supported                           |             |   | Printer model                     |   |
|--|-------------|---|-----------------------------------|---|
| Message  | Status code | Return string                                     | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de,<br>X466dte,<br>X466dwe |
| Intervention Required -<br>Missing or Defective<br>Cartridge | 40412       | 31.41 Missing or<br>defective yellow<br>cartridge | X                                 | X   |
| Intervention Required -<br>Fuser Missing                     | 40416       | 80.yy Fuser<br>missing                            | X                                 | X   |
| Intervention Required -<br>Fuser Missing                     | 40416       | 87.yy Fuser<br>missing                            | X                                 | X   |

\* This message contains a subset of letters CMYK, where CMYK denotes Cyan, Magenta, Yellow, and Black cartridges, respectively.

## PJL messages for paper handling

| ✓ = Supported<br>X = Not supported                         |             |                                    | Printer model                     |  |
|--|-------------|------------------------------------|-----------------------------------|--|
| Message  | Status code | Return string                      | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de, X466dte,<br>X466dwe |
| Intervention Required -<br>Tray <x> Empty                  | 11xyy       | Tray <source #><br>Empty           | X                                 | X  |
| Intervention Required -<br>Tray <x> Missing                | 12x01       | Tray <source #><br>Missing         | X                                 | X  |
| Intervention Required -<br>Bin <x> Full                    | 15ww1       | Bin <Bin #> Full                   | X                                 | X  |
| Intervention Required -<br>Wrong Paper Size in<br>Tray <x> | 30034       | 34 Wrong Paper<br>Size in Tray <x> | X                                 | X  |
| Intervention Required -<br>Wrong Paper Size<br>Manual Feed | 30034       | 34 Wrong Paper<br>Size Manual Feed | X                                 | X  |
| Intervention Required -<br>Remove Paper All Output<br>Bins | 40019       | Remove Paper All<br>Output Bins    | X                                 | X  |
| Intervention Required -<br>Remove Paper From All<br>Bins   | 40019       | Remove paper from<br>all bins      | X                                 | X  |

| ✓ = Supported<br>X = Not supported                                  |             |   | Printer model                     |  |
|---|-------------|---|-----------------------------------|--|
| Message   | Status code | Return string   | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de, X466dte,<br>X466dwe |
| Intervention Required -<br>Remove Paper From<br><bin #>             | 40019       | Remove paper from<br>bin <bin #>  | X                                 | X  |
| Intervention Required -<br>Remove Paper <linked<br>set bin name>    | 40019       | Remove paper<br>from <linked set<br>bin name>   | X                                 | X  |
| Intervention Required -<br>Remove Paper From<br>Standard Output Bin | 40019       | Remove paper from<br>standard output<br>bin   | ✓                                 | ✓  |
| Intervention Required -<br>Remove Paper <linked<br>set bin name>    | 40019       | Remove<br>Paper <linked set<br>bin name>  | X                                 | X  |
| Intervention Required -<br>Remove Paper Outbin<br><bin #>           | 40019       | Remove Paper<br>Output Bin<br><bin #>   | X                                 | X  |
| Intervention Required -<br>Remove Paper Standard<br>Bin             | 40019       | Remove Paper<br>Standard Bin  | X                                 | X  |
| Intervention Required -<br>Photoconductor<br>Exposure Warning       | 40025       | Photoconductor<br>exposure warning  | X                                 | X  |
| Intervention Required -<br>Check <Source><br>Orientation or Guides  | 4100x       | Check <source><br>orientation or<br>guides  | X                                 | X  |
| Intervention Required -<br>Check <Source> Paper<br>Guide            | 4100x       | Check <source><br>Paper Guide   | X                                 | X  |
| Intervention Required -<br>Incorrect Media                          | 41xy        | Paper changes<br>needed   | X                                 | X  |
| Intervention Required -<br>Change Request                           | 41xyy       | Change <source><br><Custom Type<br>Name><br><Custom String><br><size><br><type><size> | X                                 | ✓  |

## Appendix B: PJI support

| ✓ = Supported<br>X = Not supported                            |             |  | Printer model                     |  |
|---|-------------|--|-----------------------------------|--|
| Message   | Status code | Return string  | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de, X466dte,<br>X466dwe |
| Intervention Required -<br>Load Manual Request                | 41xyy       | Load Manual<br><Custom Type<br>Name><br><Custom String><br><size><br><type><size>                  | ✓                                 | ✓  |
| Intervention Required -<br>Load Manual Request                | 41xyy       | Load Manual<br>Feeder<br>with <Custom Type<br>Name>  | X                                 | X  |
| Intervention Required -<br>Load Manual Request                | 41xyy       | Load Manual<br>Feeder<br>with <Custom<br>String>   | X                                 | X  |
| Intervention Required -<br>Load Manual Request                | 41xyy       | Load Manual<br>Feeder<br>with <size>   | X                                 | X  |
| Intervention Required -<br>Load Manual Request                | 41xyy       | Load Manual<br>Feeder<br>with <type><size>   | X                                 | X  |
| Intervention Required -<br>Load Request                       | 41xyy       | Load <source><br><Custom Type<br>Name><br><Custom String><br><size><br><type><size>                | ✓                                 | X  |
| Intervention Required -<br>Load Request                       | 41xyy       | Load <source><br>with <Custom Type<br>Name><br><Custom String><br>with <size><br>with <type><size> | ✓                                 | ✓  |
| Intervention Required -<br>Incorrect Media                    | 41xyy       | 34 Incorrect<br>Media  | X                                 | X  |
| Intervention Required -<br>Insert Duplex Pages &<br>Press Go. | 412yy       | Insert Duplex<br>Pages & Press Go.   | X                                 | X  |
| Intervention Required -<br>Insert Tray Request                | 4300x       | Insert Tray <x>  | X                                 | X  |

## Appendix B: PjL support

# PJL messages for paper jams

| ✓ = Supported<br>X = Not supported   | Status code | Printer model                     |  |
|--------------------------------------|-------------|-----------------------------------|--|
|                                      |             | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de, X466dte,<br>X466dwe |
| Intervention Required -<br>Paper Jam | 4200x       | X                                 | X  |
| Intervention Required -<br>Paper Jam | 4200z       | ✓                                 | ✓  |
| Intervention Required -<br>Paper Jam | 4201x       | X                                 | X  |
| Intervention Required -<br>Paper Jam | 4201z       | ✓                                 | ✓  |
| Intervention Required -<br>Paper Jam | 4202x       | X                                 | X  |
| Intervention Required -<br>Paper Jam | 4202z       | ✓                                 | ✓  |
| Intervention Required -<br>Paper Jam | 4203x       | X                                 | X  |
| Intervention Required -<br>Paper Jam | 4203z       | X                                 | X  |
| Intervention Required -<br>Paper Jam | 4204x       | X                                 | X  |
| Intervention Required -<br>Paper Jam | 4205x       | X                                 | X  |
| Intervention Required -<br>Paper Jam | 4206x       | X                                 | X  |
| Intervention Required -<br>Paper Jam | 4207x       | X                                 | X  |
| Intervention Required -<br>Paper Jam | 4208x       | X                                 | X  |
| Intervention Required -<br>Paper Jam | 4209x       | X                                 | X  |

w indicates this message includes a letter indicating a door or cover that needs to be opened.  
 x represents the number of jammed pages in the printer.  
 y represents the tray number.  
 z represents the bin number.

| ✓ = Supported<br>X = Not supported |             | Printer model                     |  |
|------------------------------------|-------------|-----------------------------------|--|
| Message                            | Status code | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de, X466dte,<br>X466dwe |
| Intervention Required - Paper Jam  | 4210x       | X                                 | X  |
| Intervention Required - Paper Jam  | 4211x       | X                                 | X  |
| Intervention Required - Paper Jam  | 4220x       | X                                 | X  |
| Intervention Required - Paper Jam  | 4221x       | X                                 | X  |
| Intervention Required - Paper Jam  | 4222x       | X                                 | X  |
| Intervention Required - Paper Jam  | 4230x       | X                                 | X  |
| Intervention Required - Paper Jam  | 4230z       | ✓                                 | ✓  |
| Intervention Required - Paper Jam  | 4231x       | X                                 | X  |
| Intervention Required - Paper Jam  | 4231z       | X                                 | X  |
| Intervention Required - Paper Jam  | 4232x       | X                                 | X  |
| Intervention Required - Paper Jam  | 4233x       | X                                 | X  |
| Intervention Required - Paper Jam  | 4234        | X                                 | X  |
| Intervention Required - Paper Jam  | 424yx       | X                                 | X  |
| Intervention Required - Paper Jam  | 424xz       | X                                 | X  |
| Intervention Required - Paper Jam  | 4241wy      | X                                 | X  |

w indicates this message includes a letter indicating a door or cover that needs to be opened.  
 x represents the number of jammed pages in the printer.  
 y represents the tray number.  
 z represents the bin number.

## Appendix B: PjL support

| ✓ = Supported<br>X = Not supported |             | Printer model                     |  |
|------------------------------------|-------------|-----------------------------------|--|
| Message                            | Status code | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de, X466dte,<br>X466dwe |
| Intervention Required - Paper Jam  | 4241z       | X                                 | X  |
| Intervention Required - Paper Jam  | 4242wy      | X                                 | X  |
| Intervention Required - Paper Jam  | 4242z       | X                                 | X  |
| Intervention Required - Paper Jam  | 4243w       | X                                 | X  |
| Intervention Required - Paper Jam  | 4243z       | X                                 | X  |
| Intervention Required - Paper Jam  | 4244wy      | X                                 | X  |
| Intervention Required - Paper Jam  | 4244z       | X                                 | X  |
| Intervention Required - Paper Jam  | 4245w       | X                                 | X  |
| Intervention Required - Paper Jam  | 4246w       | X                                 | X  |
| Intervention Required - Paper Jam  | 4247wy      | X                                 | X  |
| Intervention Required - Paper Jam  | 4248w       | X                                 | X  |
| Intervention Required - Paper Jam  | 4249w       | X                                 | X  |
| Intervention Required - Paper Jam  | 4250w       | X                                 | X  |
| Intervention Required - Paper Jam  | 4250x       | X                                 | X  |
| Intervention Required - Paper Jam  | 4250z       | ✓                                 | ✓  |

w indicates this message includes a letter indicating a door or cover that needs to be opened.  
 x represents the number of jammed pages in the printer.  
 y represents the tray number.  
 z represents the bin number.

## Appendix B: PJL support



| ✓ = Supported<br>X = Not supported |             | Printer model                     |  |
|------------------------------------|-------------|-----------------------------------|--|
| Message                            | Status code | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de, X466dte,<br>X466dwe |
| Intervention Required - Paper Jam  | 4251wy      | X                                 | X  |
| Intervention Required - Paper Jam  | 4251x       | X                                 | X  |
| Intervention Required - Paper Jam  | 4252w       | X                                 | X  |
| Intervention Required - Paper Jam  | 4253w       | X                                 | X  |
| Intervention Required - Paper Jam  | 4254wy      | X                                 | X  |
| Intervention Required - Paper Jam  | 4255        | X                                 | X  |
| Intervention Required - Paper Jam  | 4256w       | X                                 | X  |
| Intervention Required - Paper Jam  | 4257w       | X                                 | X  |
| Intervention Required - Paper Jam  | 4258w       | X                                 | X  |
| Intervention Required - Paper Jam  | 4259wy      | X                                 | X  |
| Intervention Required - Paper Jam  | 4260w       | X                                 | X  |
| Intervention Required - Paper Jam  | 4260x       | X                                 | X  |
| Intervention Required - Paper Jam  | 4260z       | X                                 | X  |
| Intervention Required - Paper Jam  | 4261w       | X                                 | X  |
| Intervention Required - Paper Jam  | 4261x       | X                                 | X  |

w indicates this message includes a letter indicating a door or cover that needs to be opened.  
x represents the number of jammed pages in the printer.  
y represents the tray number.  
z represents the bin number.

## Appendix B: PjL support

| ✓ = Supported<br>X = Not supported |             | Printer model                     |  |
|------------------------------------|-------------|-----------------------------------|--|
| Message                            | Status code | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de, X466dte,<br>X466dwe |
| Intervention Required - Paper Jam  | 427xz       | X                                 | X  |
| Intervention Required - Paper Jam  | 427zx       | X                                 | X  |
| Intervention Required - Paper Jam  | 4271        | X                                 | X  |
| Intervention Required - Paper Jam  | 4271z       | X                                 | X  |
| Intervention Required - Paper Jam  | 4272        | X                                 | X  |
| Intervention Required - Paper Jam  | 4272z       | X                                 | X  |
| Intervention Required - Paper Jam  | 4273        | X                                 | X  |
| Intervention Required - Paper Jam  | 4280w       | X                                 | X  |
| Intervention Required - Paper Jam  | 4280x       | X                                 | X  |
| Intervention Required - Paper Jam  | 4280z       | X                                 | X  |
| Intervention Required - Paper Jam  | 4281w       | X                                 | X  |
| Intervention Required - Paper Jam  | 4281x       | X                                 | X  |
| Intervention Required - Paper Jam  | 4281z       | X                                 | X  |
| Intervention Required - Paper Jam  | 4282w       | X                                 | X  |
| Intervention Required - Paper Jam  | 4282x       | X                                 | X  |

w indicates this message includes a letter indicating a door or cover that needs to be opened.  
x represents the number of jammed pages in the printer.  
y represents the tray number.  
z represents the bin number.

## Appendix B: PJL support

| ✓ = Supported<br>X = Not supported |             | Printer model                     |  |
|------------------------------------|-------------|-----------------------------------|--|
| Message                            | Status code | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de, X466dte,<br>X466dwe |
| Intervention Required - Paper Jam  | 4282z       | X                                 | X  |
| Intervention Required - Paper Jam  | 4283w       | X                                 | X  |
| Intervention Required - Paper Jam  | 4283x       | X                                 | X  |
| Intervention Required - Paper Jam  | 4283z       | X                                 | X  |
| Intervention Required - Paper Jam  | 4284w       | X                                 | X  |
| Intervention Required - Paper Jam  | 4284x       | X                                 | X  |
| Intervention Required - Paper Jam  | 4284z       | X                                 | X  |
| Intervention Required - Paper Jam  | 4285w       | X                                 | X  |
| Intervention Required - Paper Jam  | 4285z       | X                                 | X  |
| Intervention Required - Paper Jam  | 4286w       | X                                 | X  |
| Intervention Required - Paper Jam  | 4286z       | X                                 | X  |
| Intervention Required - Paper Jam  | 4287        | X                                 | X  |
| Intervention Required - Paper Jam  | 4287z       | X                                 | X  |
| Intervention Required - Paper Jam  | 4288        | X                                 | X  |
| Intervention Required - Paper Jam  | 4288z       | X                                 | X  |

w indicates this message includes a letter indicating a door or cover that needs to be opened.  
x represents the number of jammed pages in the printer.  
y represents the tray number.  
z represents the bin number.

## Appendix B: PJI support

| ✓ = Supported<br>X = Not supported   |             | Printer model                     |  |
|--|-------------|-----------------------------------|--|
| Message  | Status code | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de, X466dte,<br>X466dwe |
| Intervention Required - Paper Jam  | 4289        | X                                 | X  |
| Intervention Required - Paper Jam  | 4289z       | X                                 | X  |
| Intervention Required - Paper Jam  | 4290        | X                                 | X  |
| Intervention Required - Paper Jam  | 4291        | X                                 | X  |
| Intervention Required - Paper Jam  | 4292        | X                                 | X  |
| Intervention Required - Paper Jam  | 4293        | X                                 | X  |
| Intervention Required - Paper Jam  | 4294        | X                                 | X  |
| Intervention Required - Paper Jam  | 4295        | X                                 | X  |
| w indicates this message includes a letter indicating a door or cover that needs to be opened.<br>x represents the number of jammed pages in the printer.<br>y represents the tray number.<br>z represents the bin number. |             |                                   |  |

## Service errors

| ✓ = Supported<br>X = Not supported |            | Printer model                     |  |
|------------------------------------|------------|-----------------------------------|--|
| Message                            | Error code | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de, X466dte,<br>X466dwe |
| ALL SERVICE MESSAGES               | 50000      | X                                 | X  |

## Device attendance messages

| ✓ = Supported<br>X = Not supported | Printer model                     |  |
|------------------------------------|-----------------------------------|--|
|                                    | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de, X466dte,<br>X466dwe |
| Message                            |                                   |  |
| OPMSG                              | ✓                                 | ✓  |
| RDYMSG                             | ✓                                 | ✓  |
| STMSG                              | ✓                                 | ✓  |

## Lexmark-unique PJI commands

| ✓ = Supported<br>X = Not supported | Printer model                     |  |
|------------------------------------|-----------------------------------|--|
|                                    | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de, X466dte,<br>X466dwe |
| Command                            |                                   |  |
| LBEEP                              | ✓                                 | ✓  |
| LCLOSEFILE                         | ✓                                 | ✓  |
| LDEFRAG                            | ✓                                 | ✓  |
| LDELETEFILE                        | ✓                                 | ✓  |
| LDOWNLOADTARGET                    | ✓                                 | ✓  |
| LENGINEPRT                         | ✓                                 | ✓  |
| LESCAPECHAR                        | ✓                                 | ✓  |
| LFAX PHONENUMBER                   | X                                 | X  |
| LFORMAT                            | ✓                                 | ✓  |
| LINITIALIZEPRINTER                 | ✓                                 | ✓  |
| LOPENFILE                          | ✓                                 | ✓  |
| LPORTROTATE                        | ✓                                 | ✓  |
| LPRINT testpage                    | ✓                                 | ✓  |
| LPRINTDIRECTORY                    | ✓                                 | ✓  |
| LPRINTMENUS                        | ✓                                 | ✓  |

| ✓ = Supported<br>X = Not supported | Printer model                     |  |
|------------------------------------|-----------------------------------|--|
|                                    | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de, X466dte,<br>X466dwe |
| Command                            |                                   |  |
| LPRINTPCLFONTS                     | ✓                                 | ✓  |
| LPRINTPSFONTS                      | ✓                                 | ✓  |
| LPRINTTESTPAGE                     | ✓                                 | ✓  |
| LPRINTDIAG1TEST                    | ✓                                 | ✓  |
| LPRINTDIAG2TEST                    | ✓                                 | ✓  |
| LPRINTDIAG3TEST                    | ✓                                 | ✓  |
| LREADFILE                          | ✓                                 | ✓  |
| LRENAMEFILE                        | ✓                                 | ✓  |
| LRUNFILE                           | ✓                                 | ✓  |
| LWRITEFILE                         | ✓                                 | ✓  |

## File and device protection commands

| ✓ = Supported<br>X = Not supported | Printer model                     |  |
|------------------------------------|-----------------------------------|--|
|                                    | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de, X466dte,<br>X466dwe |
| Command                            |                                   |  |
| LBPASSPASSWORD KEY                 | ✓                                 | ✓  |
| LDECLARE LRESOURCE                 | ✓                                 | ✓  |
| LDELETEPASSWORD                    | ✓                                 | ✓  |
| LQUERYSEED                         | ✓                                 | ✓  |

# Appendix C: PostScript support

## Supplemental operators

| Operator name           | Printer model                     |  |
|-------------------------|-----------------------------------|--|
|                         | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de, X466dte,<br>X466dwe |
| appletalktype           | ✓                                 | ✓  |
| buildtime               | ✓                                 | ✓  |
| byteorder               | ✓                                 | ✓  |
| checkpassword           | ✓                                 | ✓  |
| currentfilenameextend   | ✓                                 | ✓  |
| currentmanualduplexmode | ✓                                 | ✓  |
| currentuniversalsize    | ✓                                 | ✓  |
| defaulttimeouts         | X                                 | X  |
| deletefile              | ✓                                 | ✓  |
| devcontrol              | ✓                                 | ✓  |
| devdismount             | ✓                                 | ✓  |
| devforall               | ✓                                 | ✓  |
| devformat               | ✓                                 | ✓  |
| devmount                | ✓                                 | ✓  |
| devstatus               | ✓                                 | ✓  |
| diskonline              | ✓                                 | ✓  |
| diskstatus              | ✓                                 | ✓  |
| displayoperatormsg      | ✓                                 | ✓  |
| doidlefonts             | ✓                                 | ✓  |
| dojamrecovery           | ✓                                 | ✓  |
| doprinterrors           | ✓                                 | ✓  |
| doret                   | X                                 | X  |

| ✓ = Supported<br>X = Not supported | Printer model                     |  |
|------------------------------------|-----------------------------------|--|
|                                    | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de, X466dte,<br>X466dwe |
| dostartpage                        | ✓                                 | ✓  |
| dosysstart                         | ✓                                 | ✓  |
| duplexer                           | ✓                                 | ✓  |
| duplexmode                         | ✓                                 | ✓  |
| enginesync                         | ✓                                 | ✓  |
| file                               | ✓                                 | ✓  |
| filenameforall                     | ✓                                 | ✓  |
| fileposition                       | ✓                                 | ✓  |
| firstside                          | ✓                                 | ✓  |
| fontnonzerowinding                 | ✓                                 | ✓  |
| hardwareiomode                     | ✓                                 | ✓  |
| idlefonts                          | ✓                                 | ✓  |
| ignoresize                         | ✓                                 | ✓  |
| initializedisk                     | ✓                                 | ✓  |
| jobname                            | ✓                                 | ✓  |
| jobsources                         | ✓                                 | ✓  |
| jobtimeout                         | ✓                                 | ✓  |
| manualfeed                         | ✓                                 | ✓  |
| manualfeedtimeout                  | ✓                                 | ✓  |
| newsheet                           | ✓                                 | ✓  |
| pagecount                          | ✓                                 | ✓  |
| pagesprinted                       | ✓                                 | ✓  |
| papertray                          | ✓                                 | ✓  |
| printername                        | ✓                                 | ✓  |
| product                            | ✓                                 | ✓  |
| PS2fonts                           | ✓                                 | ✓  |

## Appendix C: PostScript support



| <b>✓ = Supported</b><br><b>X = Not supported</b> | Printer model                     |  |
|--|-----------------------------------|--|
|  | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de, X466dte,<br>X466dwe |
| PS3fonts   | ✓                                 | ✓  |
| quiet  | ✓                                 | ✓  |
| ramsize  | ✓                                 | ✓  |
| realformat                                       | ✓                                 | ✓  |
| renamefile                                       | ✓                                 | ✓  |
| resolution                                       | ✓                                 | ✓  |
| revision   | ✓                                 | ✓  |
| sccbatch   | ✓                                 | ✓  |
| sccinteractive                                   | ✓                                 | ✓  |
| setcoverpage                                     | X                                 | X  |
| setdefaulttimeouts                               | ✓                                 | ✓  |
| setdoidlefonts                                   | ✓                                 | ✓  |
| setdojamrecovery                                 | ✓                                 | ✓  |
| setdoprinterrors                                 | ✓                                 | ✓  |
| setdoret   | X                                 | X  |
| setdostartpage                                   | ✓                                 | ✓  |
| setdosysstart                                    | ✓                                 | ✓  |
| setduplexmode                                    | ✓                                 | ✓  |
| setenginesync                                    | ✓                                 | ✓  |
| setethernetaddress                               | ✓                                 | ✓  |
| setfilenameextend                                | ✓                                 | ✓  |
| setfileposition                                  | ✓                                 | ✓  |
| sethardwareiomode                                | ✓                                 | ✓  |
| setidlefonts                                     | ✓                                 | ✓  |
| setignoresize                                    | ✓                                 | ✓  |
| setjobtimeout                                    | X                                 | X  |

## Appendix C: PostScript support

| ✓ = Supported<br>X = Not supported | Printer model                     |  |
|------------------------------------|-----------------------------------|--|
|                                    | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de, X466dte,<br>X466dwe |
| Operator name                      |                                   |  |
| setmanualduplexmode                | ✓                                 | ✓  |
| setpapertray                       | ✓                                 | ✓  |
| setprintername                     | ✓                                 | ✓  |
| setquiet                           | ✓                                 | ✓  |
| setresolution                      | ✓                                 | ✓  |
| setscbatch                         | ✓                                 | ✓  |
| setscinteractive                   | ✓                                 | ✓  |
| setsoftwareiomode                  | ✓                                 | ✓  |
| settumble                          | ✓                                 | ✓  |
| setuniversalsize                   | ✓                                 | ✓  |
| setuserdiskpercent                 | ✓                                 | ✓  |
| softwareiomode                     | ✓                                 | ✓  |
| tumble                             | ✓                                 | ✓  |
| userdiskpercent                    | ✓                                 | ✓  |
| waittimeout                        | ✓                                 | ✓  |

## Page device parameters

| ✓ = Supported<br>X = Not supported                              | Printer model                     |  |
|---|-----------------------------------|--|
|   | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de, X466dte,<br>X466dwe |
| Key   |                                   |  |
| BeginPage   | ✓                                 | ✓  |
| Collate   | ✓                                 | ✓  |
| DeferredMediaSelection  | ✓                                 | ✓  |
| DeviceRenderingInfo   | ✓                                 | ✓  |
| <ul style="list-style-type: none"> <li>AutoMediaType</li> </ul> | ✓                                 | ✓  |

| ✓ = Supported<br>X = Not supported | Printer model                     |  |
|------------------------------------|-----------------------------------|--|
|                                    | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de, X466dte,<br>X466dwe |
| • ColorBalance                     | X                                 | X  |
| • ColorCorrection                  | ✓                                 | ✓  |
| • ColorSaver                       | X                                 | X  |
| • DefaultPoliciesPageSize          | X                                 | X  |
| • EdgeToEdge                       | ✓                                 | ✓  |
| • ImageBrightness                  | ✓                                 | ✓  |
| • ImageContrast                    | ✓                                 | ✓  |
| • ImageEnhancement                 | ✓                                 | ✓  |
| • ImageEnhancementType             | ✓                                 | ✓  |
| • ImageSaturation                  | X                                 | X  |
| • LineDetail                       | ✓                                 | ✓  |
| • ManualColor                      | X                                 | X  |
| • PrintDarkness                    | ✓                                 | ✓  |
| • PictureGrade                     | X                                 | X  |
| • PrintQuality                     | X                                 | X  |
| • Screening                        | X                                 | X  |
| - ColorGrade                       | X                                 | X  |
| - IET                              | X                                 | X  |
| - IETImagesOnly                    | X                                 | X  |
| - IETPictureGrade                  | X                                 | X  |
| - None                             | X                                 | X  |
| - PictureGrade                     | X                                 | X  |
| • SubstituteSize                   | ✓                                 | ✓  |
| • TonerSaver                       | ✓                                 | ✓  |
| • Type                             | ✓                                 | ✓  |
| Duplex                             | ✓                                 | ✓  |
| EndPage                            | ✓                                 | ✓  |
| ExitJamRecovery                    | ✓                                 | ✓  |

## Appendix C: PostScript support

| ✓ = Supported<br>X = Not supported | Printer model                     |  |
|------------------------------------|-----------------------------------|--|
|                                    | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de, X466dte,<br>X466dwe |
| Key                                |                                   |  |
| HWRResolution                      | ✓                                 | ✓  |
| ImagingBBox                        | ✓                                 | ✓  |
| InputAttributes                    | ✓                                 | ✓  |
| • 0 - Tray 1                       | ✓                                 | ✓  |
| • 1 - Tray 2                       | ✓                                 | ✓  |
| • 2 - Envelope Feeder              | ✓                                 | ✓  |
| • 3 - Tray 3                       | ✓                                 | ✓  |
| • 4 - Multipurpose Feeder          | ✓                                 | ✓  |
| • 5 - Tray 4                       | ✓                                 | ✓  |
| • 6 - Tray 5                       | ✓                                 | ✓  |
| - InputLocation                    | ✓                                 | ✓  |
| - MatchAll                         | ✓                                 | ✓  |
| - MediaColor                       | ✓                                 | ✓  |
| - MediaType                        | ✓                                 | ✓  |
| - MediaWeight                      | ✓                                 | ✓  |
| - PageSize                         | ✓                                 | ✓  |
| • Mode                             | ✓                                 | ✓  |
| • Priority                         | ✓                                 | ✓  |
| Install                            | ✓                                 | ✓  |
| Jog                                | ✓                                 | ✓  |
| ManualFeed                         | ✓                                 | ✓  |
| ManualFeedTimeout                  | ✓                                 | ✓  |
| MediaColor                         | ✓                                 | ✓  |
| MediaPosition                      | ✓                                 | ✓  |
| MediaType                          | ✓                                 | ✓  |
| MediaWeight                        | ✓                                 | ✓  |

## Appendix C: PostScript support

| ✓ = Supported<br>X = Not supported | Printer model                     |  |
|------------------------------------|-----------------------------------|--|
|                                    | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de, X466dte,<br>X466dwe |
| Key                                |                                   |  |
| NumCopies                          | ✓                                 | ✓  |
| Nup                                | ✓                                 | ✓  |
| NupDetails                         | ✓                                 | ✓  |
| • Border                           | ✓                                 | ✓  |
| • Columns                          | ✓                                 | ✓  |
| • LandscapeOverride                | ✓                                 | ✓  |
| • Order                            | ✓                                 | ✓  |
| • Orientation                      | ✓                                 | ✓  |
| • Rows                             | ✓                                 | ✓  |
| • Type                             | ✓                                 | ✓  |
| OutputAttributes                   | ✓                                 | ✓  |
| • 0 - Standard Bin                 | ✓                                 | ✓  |
| • 1 - Optional Bin 1               | X                                 | X  |
| • 2 - Optional Bin 2               | X                                 | X  |
| • 3 - Optional Bin 3               | X                                 | X  |
| • 4 - Optional Bin 4               | X                                 | X  |
| • 5 - Optional Bin 5               | X                                 | X  |
| • 6 - Optional Bin 6               | X                                 | X  |
| • 7 - Optional Bin 7               | X                                 | X  |
| • 8 - Optional Bin 8               | X                                 | X  |
| • 9 - Optional Bin 9               | X                                 | X  |
| • 10 - Optional Bin 10             | X                                 | X  |
| - OutputLocation                   | ✓                                 | ✓  |
| - OutputType                       | ✓                                 | ✓  |
| - Priority                         | ✓                                 | ✓  |
| OutputPage                         | ✓                                 | ✓  |
| OutputType                         | ✓                                 | ✓  |

## Appendix C: PostScript support

| ✓ = Supported<br>X = Not supported | Printer model                     |  |
|------------------------------------|-----------------------------------|--|
|                                    | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de, X466dte,<br>X466dwe |
| Key                                |                                   |  |
| PageDeviceName                     | ✓                                 | ✓  |
| PageSize                           | ✓                                 | ✓  |
| Policies                           | ✓                                 | ✓  |
| • PolicyNotFound                   | ✓                                 | ✓  |
| • PolicyReport                     | ✓                                 | ✓  |
| • PageSize                         | ✓                                 | ✓  |
| PostRenderingEnhance               | X                                 | X  |
| PostRenderingEnhanceDetails        | X                                 | X  |
| • REValue                          | X                                 | X  |
| • Type                             | X                                 | X  |
| PowerSave                          | ✓                                 | ✓  |
| ProcessColorModel                  | X                                 | X  |
| Punch                              | X                                 | X  |
| SlipSheet                          | ✓                                 | ✓  |
| SlipSheetDetails                   | ✓                                 | ✓  |
| • SlipSheetSource                  | ✓                                 | ✓  |
| • Type                             | ✓                                 | ✓  |
| Staple                             | X                                 | X  |
| TraySwitch                         | ✓                                 | ✓  |
| Tumble                             | ✓                                 | ✓  |
| UniversalDetails                   | ✓                                 | ✓  |
| • Orientation                      | ✓                                 | ✓  |
| • PageSize                         | ✓                                 | ✓  |
| • Prompt                           | ✓                                 | ✓  |
| • Type                             | ✓                                 | ✓  |

## Appendix C: PostScript support

# User interpreter parameters

| ✓ = Supported<br>X = Not supported |   | Printer model                     |  |
|------------------------------------|---|-----------------------------------|--|
| Key                                | Default                                 | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de, X466dte,<br>X466dwe |
| AccurateScreens                    | false                                   | ✓                                 | ✓  |
| CollatedCopies                     | Collation - Collated Copies (QTY) value | ✓                                 | ✓  |
| HalftoneMode                       | 0                                       | ✓                                 | ✓  |
| IdiomRecognition                   | true                                    | ✓                                 | ✓  |
| JobName                            | ()                                      | ✓                                 | ✓  |
| JobTimeout                         | JobTimeout system parameter             | ✓                                 | ✓  |
| MaxDictStack                       | 255                                     | ✓                                 | ✓  |
| MaxExecStack                       | 10015                                   | ✓                                 | ✓  |
| MaxFontItem                        | 12500                                   | ✓                                 | ✓  |
| MaxFormItem                        | 100000                                  | ✓                                 | ✓  |
| MaxLocalVM                         | 2147483647                              | ✓                                 | ✓  |
| MaxOpStack                         | 100000                                  | ✓                                 | ✓  |
| MaxPatternItem                     | 20000                                   | ✓                                 | ✓  |
| MaxScreenItem                      | 48000                                   | ✓                                 | ✓  |
| MaxSuperScreen                     | 1024                                    | ✓                                 | ✓  |
| MaxUPathItem                       | 5000                                    | ✓                                 | ✓  |
| MinFontCompress                    | 2147483647                              | ✓                                 | ✓  |
| PageCount                          | 0                                       | ✓                                 | ✓  |
| UseOldcopypage                     | false                                   | ✓                                 | ✓  |
| VMReclaim                          | 0                                       | ✓                                 | ✓  |
| VMThreshold                        | 25000 per MB of RAM                     | ✓                                 | ✓  |
| WaitTimeout                        | WaitTimeout system parameter            | ✓                                 | ✓  |

# System interpreter parameters

| ✓ = Supported<br>X = Not supported | Printer model                                  |  |
|------------------------------------|--|--|
|                                    | T650n/dn/dtn,<br>T652n/dn/dtn,<br>T654n/dn/dtn | X651 MFP, X652 MFP,<br>X654 MFP, X656 MFP,<br>X658 MFP |
| BuildTime                          | ✓  | ✓  |
| ByteOrder                          | ✓  | ✓  |
| CurDisplayList                     | ✓  | ✓  |
| CurFontCache                       | ✓  | ✓  |
| CurFormCache                       | ✓  | ✓  |
| CurInputDevice                     | ✓  | ✓  |
| CurOutlineCache                    | ✓  | ✓  |
| CurOutputDevice                    | ✓  | ✓  |
| CurPatternCache                    | ✓  | ✓  |
| CurScreenStorage                   | ✓  | ✓  |
| CurSourceList                      | ✓  | ✓  |
| CurUPathCache                      | ✓  | ✓  |
| DisableFastProcs                   | ✓  | ✓  |
| DoPrintErrors                      | ✓  | ✓  |
| DoStartPage                        | ✓  | ✓  |
| EnableExtraFonts                   | ✓  | ✓  |
| EngineBoot                         | ✓  | ✓  |
| EngineCode                         | ✓  | ✓  |
| EngineSpeed                        | ✓  | ✓  |
| EnvironmentSave                    | ✓  | ✓  |
| FactoryDefaults                    | ✓  | ✓  |
| FatalErrorAddress                  | ✓  | ✓  |
| FontResourceDir                    | ✓  | ✓  |
| FontVersion                        | ✓  | ✓  |



| <b>✓ = Supported</b><br><b>X = Not supported</b> | Printer model                                  |  |
|--|--|--|
|  | T650n/dn/dtn,<br>T652n/dn/dtn,<br>T654n/dn/dtn | X651 MFP, X652 MFP,<br>X654 MFP, X656 MFP,<br>X658 MFP |
| Key  |  |  |
| GenericResourceDir                               | ✓  | ✓  |
| GenericResourcePathSep                           | ✓  | ✓  |
| InstalledRam                                     | ✓  | ✓  |
| JobTimeout                                       | ✓  | ✓  |
| languagelevel                                    | ✓  | ✓  |
| MaxDisplayList                                   | ✓  | ✓  |
| MaxDisplayAndSourceList                          | ✓  | ✓  |
| MaxFontCache                                     | ✓  | ✓  |
| MaxFormCache                                     | ✓  | ✓  |
| MaxImageBuffer                                   | ✓  | ✓  |
| MaxOutlineCache                                  | ✓  | ✓  |
| MaxPatternCache                                  | ✓  | ✓  |
| MaxPermanentVM                                   | ✓  | ✓  |
| MaxRasterMemory                                  | ✓  | ✓  |
| MaxScreenStorage                                 | ✓  | ✓  |
| MaxSourceList                                    | ✓  | ✓  |
| MaxUPathCache                                    | ✓  | ✓  |
| PageCount  | ✓  | ✓  |
| PanelCode  | ✓  | ✓  |
| PrinterCode                                      | ✓  | ✓  |
| PrinterName                                      | ✓  | ✓  |
| RamSize  | ✓  | ✓  |
| RealFormat                                       | ✓  | ✓  |
| Revision   | ✓  | ✓  |
| SearchBuiltinFontsFirst                          | ✓  | ✓  |
| SerialNumber                                     | ✓  | ✓  |

## Appendix C: PostScript support

| Key                  | Printer model                                  |  |
|----------------------|--|--|
|                      | T650n/dn/dtn,<br>T652n/dn/dtn,<br>T654n/dn/dtn | X651 MFP, X652 MFP,<br>X654 MFP, X656 MFP,<br>X658 MFP |
| StartJobPassword     | ✓  | ✓  |
| StartupMode          | ✓  | ✓  |
| StaticRamSize        | ✓  | ✓  |
| SystemParamsPassword | ✓  | ✓  |
| UseOldcopypage       | ✓  | ✓  |
| UseOldfonts          | ✓  | ✓  |
| ValidNV              | ✓  | ✓  |
| WaitTimeout          | ✓  | ✓  |

## Devices supported

| Device              | Printer model                     |  |
|---------------------|-----------------------------------|--|
|                     | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de, X466dte,<br>X466dwe |
| %AppSocketA%        | ✓                                 | ✓  |
| %AppSocketB%        | ✓                                 | ✓  |
| %AppSocketC%        | ✓                                 | ✓  |
| %AppSocketD%        | ✓                                 | ✓  |
| %EthernetPhysicalA% | ✓                                 | ✓  |
| %EthernetPhysicalB% | ✓                                 | ✓  |
| %EthernetPhysicalC% | ✓                                 | ✓  |
| %EthernetPhysicalD% | ✓                                 | ✓  |
| %EtherTalkA%        | ✓                                 | ✓  |
| %EtherTalkB%        | ✓                                 | ✓  |
| %EtherTalkC%        | ✓                                 | ✓  |
| %EtherTalkD%        | ✓                                 | ✓  |

| <b>✓ = Supported</b><br><b>X = Not supported</b> | Printer model                     |  |
|--|-----------------------------------|--|
|  | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de, X466dte,<br>X466dwe |
| Device   |                                   |  |
| %IP_A%   | ✓                                 | ✓  |
| %IP_B%   | ✓                                 | ✓  |
| %IP_C%   | ✓                                 | ✓  |
| %IP_D%   | ✓                                 | ✓  |
| %IR_A%   | ✓                                 | ✓  |
| %IR_B%   | ✓                                 | ✓  |
| %IR_C%   | ✓                                 | ✓  |
| %IR_D%   | ✓                                 | ✓  |
| %LexLinkA%                                       | ✓                                 | ✓  |
| %LexLinkB%                                       | ✓                                 | ✓  |
| %LexLinkC%                                       | ✓                                 | ✓  |
| %LexLinkD%                                       | ✓                                 | ✓  |
| %LocalTalkA%                                     | ✓                                 | ✓  |
| %LocalTalkB%                                     | ✓                                 | ✓  |
| %LocalTalkC%                                     | ✓                                 | ✓  |
| %LocalTalkD%                                     | ✓                                 | ✓  |
| %LPR_A%  | ✓                                 | ✓  |
| %LPR_B%  | ✓                                 | ✓  |
| %LPR_C%  | ✓                                 | ✓  |
| %LPR_D%  | ✓                                 | ✓  |
| %ParallelA%                                      | ✓                                 | ✓  |
| %ParallelB%                                      | ✓                                 | ✓  |
| %ParallelC%                                      | ✓                                 | ✓  |
| %ParallelD%                                      | ✓                                 | ✓  |
| %PrintServerA%                                   | ✓                                 | ✓  |
| %PrintServerB%                                   | ✓                                 | ✓  |

## Appendix C: PostScript support

| <b>✓ = Supported</b><br><b>X = Not supported</b> | Printer model                     |  |
|--|-----------------------------------|--|
|  | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de, X466dte,<br>X466dwe |
| Device   |                                   |  |
| %PrintServerC%                                   | ✓                                 | ✓  |
| %PrintServerD%                                   | ✓                                 | ✓  |
| %RemotePrinterA%                                 | ✓                                 | ✓  |
| %RemotePrinterB%                                 | ✓                                 | ✓  |
| %RemotePrinterC%                                 | ✓                                 | ✓  |
| %RemotePrinterD%                                 | ✓                                 | ✓  |
| %SerialA%  | ✓                                 | ✓  |
| %SerialB%  | ✓                                 | ✓  |
| %SerialC%  | ✓                                 | ✓  |
| %SerialD%  | ✓                                 | ✓  |
| %TokenRingPhysicalA%                             | ✓                                 | ✓  |
| %TokenRingPhysicalB%                             | ✓                                 | ✓  |
| %TokenRingPhysicalC%                             | ✓                                 | ✓  |
| %TokenRingPhysicalD%                             | ✓                                 | ✓  |
| %TokenTalkA%                                     | ✓                                 | ✓  |
| %TokenTalkB%                                     | ✓                                 | ✓  |
| %TokenTalkC%                                     | ✓                                 | ✓  |
| %TokenTalkD%                                     | ✓                                 | ✓  |
| %USB_A%  | ✓                                 | ✓  |
| %USB_B%  | ✓                                 | ✓  |
| %USB_C%  | ✓                                 | ✓  |
| %USB_D%  | ✓                                 | ✓  |

## Appendix C: PostScript support

# Device parameters

| ✓ = Supported<br>X = Not supported   | Printer model                     |  |
|--|-----------------------------------|--|
|  | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de, X466dte,<br>X466dwe |
| <b>Key</b>   |                                   |  |
| <b>Device Parameters for the Communication Device %Parallel%, %ParallelA%, %ParallelB%, %ParallelC%, %ParallelD%</b> |                                   |  |
| DelayedOutputClose   | ✓                                 | ✓  |
| Enabled  | ✓                                 | ✓  |
| Filtering  | ✓                                 | ✓  |
| Handshake  | ✓                                 | ✓  |
| HasNames   | ✓                                 | ✓  |
| Interpreter  | ✓                                 | ✓  |
| On   | ✓                                 | ✓  |
| OutputDevice   | ✓                                 | ✓  |
| PCLSmartSwitch   | ✓                                 | ✓  |
| PortLocation   | ✓                                 | ✓  |
| PSSmartSwitch  | ✓                                 | ✓  |
| Type   | ✓                                 | ✓  |
| <b>Device Parameters for the Communication Device %Serial%, %SerialA%, %SerialB%, %SerialC%, %SerialD%</b>           |                                   |  |
| Baud   | ✓                                 | ✓  |
| CheckParity  | ✓                                 | ✓  |
| DataBits   | ✓                                 | ✓  |
| DelayedOutputClose   | ✓                                 | ✓  |
| Enabled  | ✓                                 | ✓  |
| Filtering  | ✓                                 | ✓  |
| FlowControl  | ✓                                 | ✓  |
| HasNames   | ✓                                 | ✓  |
| HonorDSR   | ✓                                 | ✓  |

| ✓ = Supported<br>X = Not supported  | Printer model                     |  |
|---|-----------------------------------|--|
|   | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de, X466dte,<br>X466dwe |
| Key   |                                   |  |
| Interpreter   | ✓                                 | ✓  |
| On  | ✓                                 | ✓  |
| Parity  | ✓                                 | ✓  |
| PCLSmartSwitch  | ✓                                 | ✓  |
| PortLocation  | ✓                                 | ✓  |
| PSSmartSwitch   | ✓                                 | ✓  |
| RobustXon   | ✓                                 | ✓  |
| SerialMode  | ✓                                 | ✓  |
| StopBits  | ✓                                 | ✓  |
| Type  | ✓                                 | ✓  |
| <b>Device Parameters for the Communication Device %LocalTalk%, %LocalTalkA%, %LocalTalkB%, %LocalTalkC%, %LocalTalkD%</b> |                                   |  |
| DelayedOutputClose  | ✓                                 | ✓  |
| Enabled   | ✓                                 | ✓  |
| Filtering   | ✓                                 | ✓  |
| HasNames  | ✓                                 | ✓  |
| Interpreter   | ✓                                 | ✓  |
| LocalTalkType   | ✓                                 | ✓  |
| NodeID  | ✓                                 | ✓  |
| On  | ✓                                 | ✓  |
| PCLSmartSwitch  | ✓                                 | ✓  |
| PortLocation  | ✓                                 | ✓  |
| PSSmartSwitch   | ✓                                 | ✓  |
| Type  | ✓                                 | ✓  |
| <b>Device Parameters for the Communication Device %EtherTalk%, %EtherTalkA%, %EtherTalkB%, %EtherTalkC%, %EtherTalkD%</b> |                                   |  |
| DelayedOutputClose  | ✓                                 | ✓  |

## Appendix C: PostScript support

| ✓ = Supported<br>X = Not supported   | Printer model                     |  |
|--|-----------------------------------|--|
|  | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de, X466dte,<br>X466dwe |
| Key  |                                   |  |
| Enabled  | ✓                                 | ✓  |
| EthernetAddress  | ✓                                 | ✓  |
| EtherTalkType  | ✓                                 | ✓  |
| EtherTalkZone  | ✓                                 | ✓  |
| Filtering  | ✓                                 | ✓  |
| HasNames   | ✓                                 | ✓  |
| Interpreter  | ✓                                 | ✓  |
| NodeID   | ✓                                 | ✓  |
| On   | ✓                                 | ✓  |
| PCLSmartSwitch   | ✓                                 | ✓  |
| PortLocation   | ✓                                 | ✓  |
| PSSmartSwitch  | ✓                                 | ✓  |
| Type   | ✓                                 | ✓  |
| <b>Device Parameters for the Communication Device %IR%, %IR_A%, %IR_B%, %IR_C%, %IR_D%</b> |                                   |  |
| DelayedOutputClose   | ✓                                 | ✓  |
| Enabled  | ✓                                 | ✓  |
| Filtering  | ✓                                 | ✓  |
| HasNames   | ✓                                 | ✓  |
| Interpreter  | ✓                                 | ✓  |
| On   | ✓                                 | ✓  |
| PCLSmartSwitch   | ✓                                 | ✓  |
| PortLocation   | ✓                                 | ✓  |
| PSSmartSwitch  | ✓                                 | ✓  |
| Type   | ✓                                 | ✓  |

## Appendix C: PostScript support

| ✓ = Supported<br>X = Not supported  | Printer model                     |  |
|---|-----------------------------------|--|
|   | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de, X466dte,<br>X466dwe |
| Key   |                                   |  |
| <b>Device Parameters for the Communication Device %USB%, %USB_A%, %USB_B%, %USB_C%, %USB_D%</b>                           |                                   |  |
| DelayedOutputClose  | ✓                                 | ✓  |
| Enabled   | ✓                                 | ✓  |
| Filtering   | ✓                                 | ✓  |
| HasNames  | ✓                                 | ✓  |
| Interpreter   | ✓                                 | ✓  |
| On  | ✓                                 | ✓  |
| PCLSmartSwitch  | ✓                                 | ✓  |
| PortLocation  | ✓                                 | ✓  |
| PSSmartSwitch   | ✓                                 | ✓  |
| Type  | ✓                                 | ✓  |
| <b>Device Parameters for the Communication Device %TokenTalk%, %TokenTalkA%, %TokenTalkB%, %TokenTalkC%, %TokenTalkD%</b> |                                   |  |
| Address   | ✓                                 | ✓  |
| Bridging  | ✓                                 | ✓  |
| DelayedOutputClose  | ✓                                 | ✓  |
| Enabled   | ✓                                 | ✓  |
| Filtering   | ✓                                 | ✓  |
| HasNames  | ✓                                 | ✓  |
| Interpreter   | ✓                                 | ✓  |
| NodeID  | ✓                                 | ✓  |
| On  | ✓                                 | ✓  |
| PCLSmartSwitch  | ✓                                 | ✓  |
| PortLocation  | ✓                                 | ✓  |
| PSSmartSwitch   | ✓                                 | ✓  |

## Appendix C: PostScript support



| ✓ = Supported<br>X = Not supported  | Printer model                     |  |
|---|-----------------------------------|--|
|   | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de, X466dte,<br>X466dwe |
| Key   |                                   |  |
| TokenTalkType   | ✓                                 | ✓  |
| Type  | ✓                                 | ✓  |
| Zone  | ✓                                 | ✓  |
| <b>Device Parameters for the Communication Device %AppSocket%, %AppSocketA%, %AppSocketB%, %AppSocketC%, %AppSocketD%</b>                     |                                   |  |
| DelayedOutputClose  | ✓                                 | ✓  |
| Enabled   | ✓                                 | ✓  |
| Filtering   | ✓                                 | ✓  |
| HasNames  | ✓                                 | ✓  |
| Interpreter   | ✓                                 | ✓  |
| On  | ✓                                 | ✓  |
| PortLocation  | ✓                                 | ✓  |
| Type  | ✓                                 | ✓  |
| <b>Device Parameters for the Communication Device %RemotePrinter%, %RemotePrinterA%, %RemotePrinterB%, %RemotePrinterC%, %RemotePrinterD%</b> |                                   |  |
| DelayedOutputClose  | ✓                                 | ✓  |
| Enabled   | ✓                                 | ✓  |
| Filtering   | ✓                                 | ✓  |
| HasNames  | ✓                                 | ✓  |
| Interpreter   | ✓                                 | ✓  |
| On  | ✓                                 | ✓  |
| PortLocation  | ✓                                 | ✓  |
| Type  | ✓                                 | ✓  |
| <b>Device Parameters for the Communication Device %PrintServer%, %PrintServerA%, %PrintServerB%, %PrintServerC%, %PrintServerD%</b>           |                                   |  |
| DelayedOutputClose  | ✓                                 | ✓  |

## Appendix C: PostScript support

| ✓ = Supported<br>X = Not supported  | Printer model                     |  |
|---|-----------------------------------|--|
|   | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de, X466dte,<br>X466dwe |
| Key   |                                   |  |
| Enabled   | ✓                                 | ✓  |
| Filtering   | ✓                                 | ✓  |
| HasNames  | ✓                                 | ✓  |
| Interpreter   | ✓                                 | ✓  |
| On  | ✓                                 | ✓  |
| PortLocation  | ✓                                 | ✓  |
| Type  | ✓                                 | ✓  |
| <b>Device Parameters for the Communication Device %LPR%, %LPR_A%, %LPR_B%, %LPR_C%, %LPR_D%</b>                 |                                   |  |
| Enabled   | ✓                                 | ✓  |
| Filtering   | ✓                                 | ✓  |
| HasNames  | ✓                                 | ✓  |
| Interpreter   | ✓                                 | ✓  |
| On  | ✓                                 | ✓  |
| PortLocation  | ✓                                 | ✓  |
| Type  | ✓                                 | ✓  |
| <b>Device Parameters for the Communication Device %LexLink%, %LexLinkA%, %LexLinkB%, %LexLinkC%, %LexLinkD%</b> |                                   |  |
| DelayedOutputClose  | ✓                                 | ✓  |
| Enabled   | ✓                                 | ✓  |
| HasNames  | ✓                                 | ✓  |
| Interpreter   | ✓                                 | ✓  |
| On  | ✓                                 | ✓  |
| PortLocation  | ✓                                 | ✓  |
| Type  | ✓                                 | ✓  |

## Appendix C: PostScript support

| ✓ = Supported<br>X = Not supported  | Printer model                     |  |
|---|-----------------------------------|--|
|   | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de, X466dte,<br>X466dwe |
| <b>Key</b>  |                                   |  |
| <b>Device Parameters for the Communication Device %IP%, %IP_A%, %IP_B%, %IP_C%, %IP_D%</b>  |                                   |  |
| GatewayAddress  | ✓                                 | ✓  |
| IPAddress   | ✓                                 | ✓  |
| IPAddressDynamic  | ✓                                 | ✓  |
| NetworkMask   | ✓                                 | ✓  |
| On  | ✓                                 | ✓  |
| Physical  | ✓                                 | ✓  |
| PortLocation  | ✓                                 | ✓  |
| Type  | ✓                                 | ✓  |
| <b>Device Parameters for the Communication Device %EthernetPhysical%, %EthernetPhysicalA%, %EthernetPhysicalB%, %EthernetPhysicalC%, %EthernetPhysicalD%</b>      |                                   |  |
| EthernetAddress   | ✓                                 | ✓  |
| On  | ✓                                 | ✓  |
| PortLocation  | ✓                                 | ✓  |
| Type  | ✓                                 | ✓  |
| <b>Device Parameters for the Communication Device %TokenRingPhysical%, %TokenRingPhysicalA%, %TokenRingPhysicalB%, %TokenRingPhysicalC%, %TokenRingPhysicalD%</b> |                                   |  |
| Address   | ✓                                 | ✓  |
| On  | ✓                                 | ✓  |
| PortLocation  | ✓                                 | ✓  |
| Speed   | ✓                                 | ✓  |
| Type  | ✓                                 | ✓  |
| <b>Device Parameters for the Parameters Device %Engine%</b>   |                                   |  |
| BSizeStandard   | ✓                                 | ✓  |

## Appendix C: PostScript support

| ✓ = Supported<br>X = Not supported  | Printer model                     |  |
|---|-----------------------------------|--|
|   | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de, X466dte,<br>X466dwe |
| Key   |                                   |  |
| Darkness  | ✓                                 | ✓  |
| PageCount   | ✓                                 | ✓  |
| TimeToStandby   | ✓                                 | ✓  |
| Type  | ✓                                 | ✓  |
| <b>Device Parameters for the Parameters Device %Console%</b>  |                                   |  |
| Language  | ✓                                 | ✓  |
| Type  | ✓                                 | ✓  |
| <b>Device Parameters for the Parameters Device %Calendar%, %CalendarA%, %CalendarB%, %CalendarC%, %CalendarD%</b> |                                   |  |
| Day   | ✓                                 | ✓  |
| Hour  | ✓                                 | ✓  |
| Minute  | ✓                                 | ✓  |
| Month   | ✓                                 | ✓  |
| Running   | ✓                                 | ✓  |
| Second  | ✓                                 | ✓  |
| Type  | ✓                                 | ✓  |
| Year  | ✓                                 | ✓  |
| DateTime  | ✓                                 | ✓  |
| DayOfWeekLong   | ✓                                 | ✓  |
| DayOfWeekNum  | ✓                                 | ✓  |
| DayOfWeekShort  | ✓                                 | ✓  |
| <b>Device Parameters for the Parameters Device %disk1%</b>  |                                   |  |
| BlockSize   | ✓                                 | ✓  |
| Free  | ✓                                 | ✓  |
| HasNames  | ✓                                 | ✓  |
| InitializeAction  | ✓                                 | ✓  |

## Appendix C: PostScript support

| ✓ = Supported<br>X = Not supported                          | Printer model                     |  |
|---|-----------------------------------|--|
|   | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de, X466dte,<br>X466dwe |
| LogicalSize   | ✓                                 | ✓  |
| Mounted   | ✓                                 | ✓  |
| PhysicalSize  | ✓                                 | ✓  |
| Removable   | ✓                                 | ✓  |
| Searchable  | ✓                                 | ✓  |
| SearchOrder   | ✓                                 | ✓  |
| Type  | ✓                                 | ✓  |
| Writeable   | ✓                                 | ✓  |
| <b>Device Parameters for the Parameters Device %flash1%</b> |                                   |  |
| BlockSize   | ✓                                 | ✓  |
| Free  | ✓                                 | ✓  |
| HasNames  | ✓                                 | ✓  |
| InitializeAction  | ✓                                 | ✓  |
| LogicalSize   | ✓                                 | ✓  |
| Mounted   | ✓                                 | ✓  |
| PhysicalSize  | ✓                                 | ✓  |
| Removable   | ✓                                 | ✓  |
| Searchable  | ✓                                 | ✓  |
| SearchOrder   | ✓                                 | ✓  |
| Type  | ✓                                 | ✓  |
| Writeable   | ✓                                 | ✓  |
| <b>Device Parameters for the Parameters Device %rom%</b>    |                                   |  |
| BlockSize   | ✓                                 | ✓  |
| Free  | ✓                                 | ✓  |
| HasNames  | ✓                                 | ✓  |
| InitializeAction  | ✓                                 | ✓  |

## Appendix C: PostScript support

| Key          | Printer model                     |  |
|--------------|-----------------------------------|--|
|              | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de, X466dte,<br>X466dwe |
| LogicalSize  | ✓                                 | ✓  |
| Mounted      | ✓                                 | ✓  |
| PhysicalSize | ✓                                 | ✓  |
| Removable    | ✓                                 | ✓  |
| Searchable   | ✓                                 | ✓  |
| SearchOrder  | ✓                                 | ✓  |
| Type         | ✓                                 | ✓  |
| Writeable    | ✓                                 | ✓  |

## PostScript message keys commands

| Key    | Printer model                     |  |
|--------|-----------------------------------|--|
|        | X264dn, X363dn,<br>X364dn, X364dw | X463de, X464de,<br>X466de, X466dte,<br>X466dwe |
| job    | ✓                                 | ✓  |
| status | ✓                                 | ✓  |
| source | ✓                                 | ✓  |

# Index

## A

air temperature ranges 19  
airflow requirement 17  
altitude specifications 20  
atmospheric pressure 20

## C

clearance requirements 19  
commands  
PJL, file and device protection 78  
PJL, Lexmark-unique 77  
PostScript, message keys 102  
commands supported  
GL/2 27  
PCL emulation 21  
PJL, common variables for both languages 31  
PJL, common variables for PCL emulation 43  
PJL, common variables for PostScript emulation 44  
PJL, Status Readback 45  
PJL, unique variables for both languages 33  
PJL, unique variables for LRESOURCE 44  
PJL, unique variables for PCL emulation 43  
PJL, unique variables for PostScript emulation 44  
PJL, USTATUS variables 45

## D

devices supported  
PostScript 90  
dimensions, printer 19

## E

electrical specifications 18  
envelope sizes  
support in PostScript 14  
envelope sizes supported  
Lexmark X264 8  
Lexmark X36x 8  
Lexmark X46x 8  
envelope tray support  
PostScript operators 15

environmental conditions 19  
errors  
PJL, service 76

## F

finding information  
customer support 6  
publications 6

## G

GL/2  
commands supported 27

## H

humidity ranges 19

## L

letter meanings 5  
logical page  
PCL emulation 7

## M

meanings, letters after model number 5  
messages  
PJL, attendance conditions 52  
PJL, auto-continuable conditions 46  
PJL, device attendance 77  
PJL, paper handling 67  
PJL, paper jams 70  
model numbers  
understanding letters 5

## N

noise emission levels 17

## O

operators, envelope sizes  
PostScript 14

## P

page, printable  
PCL emulation 7  
paper sizes supported  
Lexmark X264 8

Lexmark X36x 8  
Lexmark X46x 8  
paper sizes, PostScript  
supported by printer 11  
paper tray  
operators, PostScript 12, 14  
support in PostScript 12  
parameters  
PostScript, device 93  
PostScript, page device 82  
PostScript, system interpreter 88  
PostScript, user interpreter 87  
PCL emulation  
commands supported 21  
PCL emulation, paper and envelope dimensions  
Lexmark X264 8  
Lexmark X36x 8  
Lexmark X46x 8  
physical page  
PCL emulation 7  
physical specifications 19  
PJL commands  
common variables, both languages 31  
common variables, PCL emulation 43  
common variables, PostScript emulation 44  
file and device protection 78  
Lexmark-unique 77  
Status Readback 45  
unique variables, both languages 33  
unique variables, LRESOURCE 44  
unique variables, PCL emulation 43  
unique variables, PostScript emulation 44  
USTATUS variables 45  
PJL commands, information location  
Printer Languages and Interfaces Technical Reference 10  
PJL errors  
service errors 76  
PJL messages  
attendance conditions 52

- auto-continuable conditions 46
- device attendance 77
- paper handling 67
- paper jams 70
- PostScript
  - device parameters 93
  - devices supported 90
  - operators, envelope sizes 14
  - page device parameters 82
  - supplemental operators 79
  - supported paper sizes 11
  - tray operators 12
- PostScript commands
  - message keys 102
- PostScript operators
  - envelope tray support 15
- PostScript parameters
  - system interpreter 88
  - user interpreter 87
- power requirements 18
- printable areas 7
- printer specifications 19
  - airflow requirement 17
  - altitude 20
  - atmospheric pressure 20
  - clearance requirements 19
  - electrical 18
  - environmental conditions 19
  - noise emission levels 17
  - power requirements 18

## **R**

- required clearance 19

## **S**

- size, printer 19
- supplemental operators
  - PostScript 79

## **T**

- tray operators
  - PostScript 12

## **W**

- weight, printer 19



## Free Manuals Download Website

<http://myh66.com>

<http://usermanuals.us>

<http://www.somanuals.com>

<http://www.4manuals.cc>

<http://www.manual-lib.com>

<http://www.404manual.com>

<http://www.luxmanual.com>

<http://aubethermostatmanual.com>

Golf course search by state

<http://golfingnear.com>

Email search by domain

<http://emailbydomain.com>

Auto manuals search

<http://auto.somanuals.com>

TV manuals search

<http://tv.somanuals.com>